Discord Bridge - Setup Guide

AI Assistant | Discord Bridge | U5 release candidate | October 2026

1. Before you start

Requires an AI Assistant Pro subscription, an assistant you own, a Discord account, a Discord server you manage, and a computer or server to run the Python bridge. Setup is available on the website and in the Android/iOS mobile application. The mobile app prepares and shares the ZIP; it does not run the Discord bot itself.

Use Python 3.13 (as documented by the bridge), with pip available. An always-on computer or server is recommended for continuous bot availability.

2. Create the Discord application

Open https://discord.com/developers/applications and create an application. Add a Bot. Under Bot > Privileged Gateway Intents, enable Message Content Intent. Copy the bot token privately.

Invite the bot to an explicitly selected server with View Channels and Send Messages. Add Send Messages in Threads only if needed. Never grant Administrator. Restrict the bot to intended channels.

3. Generate your private ZIP

Website: sign in, open the relevant assistant, then Discord Setup. Mobile: open the assistant and select Discord Setup. A Pro subscription is required to create a bridge.

Paste your Discord bot token, create the integration and download (web) or share/save (mobile) discord_bridge.zip. The ZIP contains bridge.py, backend_url.py, requirements.txt, README.txt, Setup_Guide.pdf, Commands_Guide.pdf and a generated .env.

The ZIP contains BOTH the Discord bot token and an assistant-scoped Discord credential. Do not upload it to GitHub, email it, share it publicly or post it in Discord.

4. Install and run

On your computer/server, extract the ZIP. Open a terminal in the extracted discord_bridge directory and install the requirements:

```
python -m pip install -r requirements.txt
```

Ensure .env is beside bridge.py, then start the bridge:

```
python bridge.py
```

Leave the process running. The console should display "Discord bridge connected." when connected. For persistent availability, use a managed process or service appropriate to your server.

5. Configuration and security

The generated .env contains DISCORD_TOKEN, DJANGO_API_TOKEN, DJANGO_BOT_ID and DJANGO_BACKEND. DJANGO_API_TOKEN is a Discord integration credential, NOT your customer API Access key or mobile login token.

DJANGO_BACKEND must point to the intended HTTPS backend. Do not accidentally point test installations at production. The bridge does not follow HTTP redirects or automatically retry timed-out AI requests.

Discord channel users share the conversation in that channel and can access the selected assistant Knowledge through the bot. DMs and separate channels/threads have independent histories for the lifetime of the bridge process. Restarting starts new conversations.

6. Verify and troubleshoot

In an allowed channel, send !ping; the bot should reply Pong. Then send !ask followed by a question, mention the bot with a question, or send a DM.

No response? Confirm the bridge process is running, Message Content Intent is enabled, channel permissions are correct, the Discord token is valid, and the configured backend is reachable. AI access also requires active Pro entitlement and remaining usage quota.

If credentials are compromised, revoke the integration from Discord Setup and generate a new ZIP. Old bridge credentials cannot be reused. The website and mobile app can both revoke integrations.

Release note

This guide reflects the U5 release-branch implementation reviewed on 14 October 2026. U5 has not yet been deployed to production; real Discord end-to-end tests and release checks are still required.