# Лабораторная работа №12

Настройка NAT

Шуваев С. А.

Российский университет дружбы народов, Москва, Россия

Информация

#### Докладчик

- Шуваев Сергей Александрович
- студент
- Российский университет дружбы народов
- · 1032224269@pfur.ru
- https://Grinders060050.github.io/ru/





Приобрести практические навыки по настройке доступа локальной сети к внешней сети посредством NAT.

- 1. Сделать первоначальную настройку маршрутизатора provider-gw-1 и коммутатора provider-sw-1 провайдера: задать имя, настроить доступ по паролю и т.п.
- 2. Настроить интерфейсы маршрутизатора provider-gw-1 и коммутатора provider-sw-1 провайдера.
- 3. Настроить интерфейсы маршрутизатора сети «Донская» для доступа к сети провайдера.
- 4. Настроить на маршрутизаторе сети «Донская» NAT с правилами.
- 5. Настроить доступ из внешней сети в локальную сеть организации.
- 6. Проверить работоспособность заданных настроек.
- 7. При выполнении работы необходимо учитывать соглашение об именовании.

```
Router (config-line) #password cisco
Router (config-line) #login
Router (config-line) #exit
Router (config) #exit
Router#
%SYS-5-CONFIG I: Configured from console by console
write m
Building configuration ...
[OK]
Routerfen
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #line console 0
Router(config-line) #password cisco
Router (config-line) #login
Router (config-line) #exit
Router (config) #exit
Router#
%SYS-5-CONFIG I: Configured from console by console
write n
% Invalid input detected at '^' marker.
Router#write m
Building configuration ...
[OK]
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #enable secret cisco
Router(config) #service password encryption
% Invalid input detected at '^' marker.
Router(config) #service password-encryption
Router(config) #username admin privilege 1 secret cisco
Router (config) #exit
Router#
%SYS-5-CONFIG I: Configured from console by console
write m
Building configuration...
[OK]
```

```
Switch>en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config) #line vtv 0 4
Switch(config-line) #password cisco
Switch (config-line) #login
Switch(config-line) #exit
Switch(config) #line console 0
Switch (config-line) #password cisco
Switch(config-line) #login
Switch(config-line) #exit
Switch(config) #enable secret cisco
Switch(config) #service password-encryption
Switch(config) #username admin privilege 1 secret c
Switch (config) #exit
Switch#
%SYS-5-CONFIG I: Configured from console by console
write m
Building configuration ...
[OK]
Switch#
```

Figure 2: Первоначальная настройка коммутатора provider-sw-1

```
Router#
Router#en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #interface f0/0
Router(config-if) #no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
exit
Router(config) #interface f0/0.4
Router (config-subif) #
%LINK-5-CHANGED: Interface FastEthernet0/0.4. changed state to up
encapsulation dot10 4
Router(config-subif) #encapsulation dot10 4
Router(config-subif) #ip address 198.51.100.1 255.255.255.240
Router(config-subif) #description msk-donskaya
Router (config-subif) #exit
Router(config) #interface f0/1
Router(config-if) #no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernetO/1, changed state to up
Router(config-if) #ip address 192.0.2.1 255.255.255.0
Router(config-if) #description internet
Router(config-if) #exit
Router (config) #exit
Router#
%SYS-5-CONFIG I: Configured from console by console
write m
Building configuration...
LOK1
D ---- #
```

```
Building configuration ...
LOKI
Switch#en
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config) #interface f0/1
Switch(config-if) #switchport mode trunk
Switch(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernetO/1, changed state to
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to
Switch (config-if) #exit
Switch(config) #interface f0/2
Switch(config-if) #switchport mode trunk
Switch(config-if) #exit
Switch(config)#vlan 4
Switch (config-vlan) #name nat
Switch (config-vlan) #exit
Switch(config) #interface vlan4
Switch(config-if)#
%LINK-5-CHANGED: Interface Vlan4, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan4, changed state to up
Switch (config-if) #no shutdown
Switch(config-if) #exit
Switch (config) #exit
Switch#
%SYS-5-CONFIG I: Configured from console by console
write m
Building configuration ...
LOKI
Switch#
```

Figure 4: Настройка интерфейсов коммутатора provider-sw-1

```
msk-donskava-shuvavev-gw-1>en
Paggword:
msk-donskava-shuvavev-gw-1#en
msk-donskava-shuvavev-gw-l#conf t
Enter configuration commands, one per line. End with CNTL/Z.
msk-donskava-shuvavev-gw-1(config) #interface f0/1
msk-donskava-shuvavev-dw-1(confid-if)ino shutdown
msk-donskava-shuvavev-gw-l(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
msk-donskava-shuvavev-gw-1(config-if)#exit
msk-donskava-shuvavev-gw-1(config) #interface f0/1.4
msk-donskava-shuvavev-gw-1(config-subif) #
%LINK-5-CHANGED: Interface FastEthernetO/1.4. changed state to up
msk-donskava-shuvavev-qw-1(config-subif) #encapsulation dot10 4
msk-donskava-shuvavev-gw-1(config-subif) #ip address 198.51.100.2 255.255.255.240
msk-donskaya-shuvayev-gw-1(config-subif) #description internet
msk-donskava-shuvavev-gw-l(config-subif) #exit
msk-donskava-shuvavev-gw-1(config) #exit
msk-donskava-shuvavev-gw-1#
$SYS-5-CONFIG I: Configured from console by console
write m
Building configuration ...
LOK1
msk-donskava-shuvavev-gw-1#en
msk-donskava-shuvavev-gw-l#conf t
Enter configuration commands, one per line. End with CNTL/Z.
msk-donskava-shuvavev-dw-1(confid) in route 0.0.0.0.0.0.0.0.0.198.51.100.1
msk-donskava-shuvavev-dw-1 (confid) texit
msk-donskava-shuvavev-gw-1#
%SYS-5-CONFIG I: Configured from console by console
write m
Building configuration ...
[OK]
msk-donskava-shuvavev-dw-1#
```

Figure 5: Настройка интерфейсов маршрутизатора msk-donskaya-gw-1

```
msk-donskaya-shuvayev-gw-1>ping 198.51.100.1

Type escape sequence to abort.

Sending 5, 100-byte ICMF Echos to 198.51.100.1, timeout is 2 seconds:
!!!!!

Success rate is 100 percent (5/5), round-trip min/avg/max = 0/2/13 ms

msk-donskaya-shuvayev-gw-1>
```

Figure 6: Проверка доступности маршрутизатора

Figure 7: Настройка пула адресов для NAT

```
msk-donskaya-shuvayev-qw-1fen
msk-donskaya-shuvayev-qw-1fen
msk-donskaya-shuvayev-qw-1feonf t
Enter configuration commands, one per line. End with CNTL/Z.
msk-donskaya-shuvayev-qw-1(config) access-list extended nat-inet
msk-donskaya-shuvayev-qw-1(config-ext-nacl) fermark dk
msk-donskaya-shuvayev-qw-1(config-ext-nacl) fermit top 10.128.3.0 0.0.0.255 host 192.0.2.11 eq 80
msk-donskaya-shuvayev-qw-1(config-ext-nacl) fermit top 10.128.3.0 0.0.0.255 host 192.0.2.12 eq 80
msk-donskaya-shuvayev-qw-1(config-ext-nacl) fermit top 10.128.5.0 0.0.0.255 host 192.0.2.14 eq 80
msk-donskaya-shuvayev-qw-1(config-ext-nacl) fermit top 10.128.5.0 0.0.0.255 host 192.0.2.14 eq 80
msk-donskaya-shuvayev-qw-1(config-ext-nacl) fermit top 10.128.6.200 any
msk-donskaya-shuvayev-qw-1(config-ext-nacl) fermit ip host 10.128.6.200 any
msk-donskaya-shuvayev-qw-1(config-ext-nacl) fermit ip host 10.128.6.200 any
```

Figure 8: Настройка списка доступа для NAT

```
msk-donskava-shuvavev-gw-1#en
msk-donskava-shuvavev-gw-1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
msk-donskaya-shuvayev-gw-l(config) #ip nat inside source list nat-inet pool ma
msk-donskava-shuvavev-gw-1(config) #int f0/0.3
msk-donskava-shuvavev-gw-l(config-subif) #ip nat inside
msk-donskaya-shuvayev-gw-1(config-subif) #interface f0/0.101
msk-donskava-shuvavev-gw-l(config-subif) #ip nat inside
msk-donskava-shuvavev-gw-1(config-subif) #exit
msk-donskaya-shuvayev-gw-l(config) #interface f0/0.102
msk-donskava-shuvavev-gw-l(config-subif) #ip nat inside
msk-donskava-shuvavev-gw-l(config-subif) #exit
msk-donskaya-shuvayev-gw-l(config) #interface f0/0.103
msk-donskava-shuvavev-gw-l(config-subif) #ip nat inside
msk-donskaya-shuvayev-gw-l(config-subif) #exit
msk-donskava-shuvavev-gw-1(config) #interface f0/0.104
msk-donskava-shuvavev-gw-l(config-subif) #ip nat inside
msk-donskava-shuvavev-gw-l(config-subif) #exit
msk-donskava-shuvavev-gw-l(config) #interface f0/1.4
msk-donskava-shuvavev-gw-l(config-subif) #ip nat outside
msk-donskava-shuvavev-gw-l(config-subif) #exit
msk-donskava-shuvavev-gw-l(config) #exit
msk-donskava-shuvavev-gw-1#
%SYS-5-CONFIG I: Configured from console by console
write m
Building configuration ...
[OK]
msk-donskava-shuvavev-gw-1#
```




Figure 10: Проверка доступности маршрутизаторов

```
msk-donskaya-shuvayev-gw-1>en
Password:

msk-donskaya-shuvayev-gw-1$conf t

msk-donskaya-shuvayev-gw-1$config|$ip nat inside source static top 10.128.0.3 20 198.51,100.3 20

msk-donskaya-shuvayev-gw-1(config)$ip nat inside source static top 10.128.0.3 21 198.51,100.3 21

msk-donskaya-shuvayev-gw-1(config)$ip nat inside source static top 10.128.0.4 25 198.51,100.3 21

msk-donskaya-shuvayev-gw-1(config)$ip nat inside source static top 10.128.0.4 25 198.51,100.4 25

msk-donskaya-shuvayev-gw-1(config)$ip nat inside source static top 10.128.0.4 110 198.51,100.4 10

3389

msk-donskaya-shuvayev-gw-1(config)$ip nat inside source static top 10.128.6.200 3389 198.51,100.10

3389
```

Figure 11: Настройка доступа из Интернета




Figure 12: Добавление ноутбука на территорию Интернет






Figure 13: Проверка доступа из Интернета по ftp



**Figure 14:** Проверка доступа из Интернета к web-серверу



**Figure 15:** Доступ dep-donskaya-1 к 192.0.2.13




Figure 16: Доступ dk-donskaya-1 к www.yandex.ru





Figure 17: Доступ dk-donskaya-1 к stud.rudn.university



**Figure 18:** Доступ adm-donskaya-1 к www.rudn.ru



В результате выполнения данной лабораторной работы я приобрел практические навыки по настройке доступа локальной сети к внешней сети посредством NAT.