

How-To Guide: Extend MDG-uMNTPLN in the U1 Data Model

Applies to

MDG EAM Solutions by Prometheus Group

Summary

SAP Master Data Governance provides an out-of-the box solution for the central management of various master data objects such as financial objects, supplier and material. In addition, SAP Master Data Governance also provides the flexibility to customize the solution, in cases where the predelivered content does not fully match customer requirements. You can use this guide to extend the MDG-U1 Data Model by a new entity type. The attribute values of the new entity type will be copied to the corresponding ERP tables (reuse option) after activation of the Change Request.

Author: Neelima Gowni

Company: Prometheus Group

Created On: September 19, 2018

Version: 1.0



Table of Contents

Introduction	3
Scenario	3
High Level Requirements	3
Governance Process	3
Implementation	4
Data Model Extension	5
Add Attributes to Existing Entity Type	5
Generate MDG Data Model-Specific Structures	7
SMT Mapping	8
SMT Mapping – Get Mapping Names from Data Model U1	8
SMT Mapping - Primary Persistence to Staging	9
SMT Mapping – Staging to Primary Persistence	10
Adjust Staging area of Linked Change Requests	11
Extending the UI Configuration	12
Add Customization to UI	12
Testing the Configuration	14



Introduction

This document describes how to extend the Data Model (U1) for Maintenance Plan by adding additional attribute "ZZREVIEWBY", "ZZREVEWDT" to the entity "MITEM".

Scenario

High Level Requirements

The business requires the new attributes called "Review Detail" as part of the MDG Maintenance Plan Data Model.

You want to extend the (Type4) entity type MITEM to include attributes: ZZREVIEWBY, ZZREVEWDT.




Figure: Data Model – Maintenance Plan (Scope of 2017 Delivery) with custom attributes "ZZREVIEWBY" and "ZZREVIEWDT"

Governance Process

The default governance process delivered with MDG is used. No changes to the governance process are necessary as part of this scenario.




Figure: Maintenance Plan processing in Master Data Governance



Implementation

Two major building blocks make up the implementation of the entity type extension. In the first phase, you extend the MDG Data Model. In the second phase, you extend the user interface to include the new entity type.

The following flow diagram displays the detailed implementation steps. It is recommended that you use it as an orientation.





Figure: Implementation steps for re-use Entity-Type extension



Data Model Extension

You want to extend the MDG Data Model (U1) for Maintenance Plan and Item by the additional attributes ZZREVIEWBY and ZZREVEWDT. The following fields from MPOS table should be modelled as attribute of entity type in MDG.




You first create the attributes ZZREVIEWBY, ZZREVEWDT in entity type MITEM.

Add Attributes to Existing Entity Type

Use the following steps to add attributes to existing Entity Type.


- 1. Log into system for cross client maintenance.
- Start Customizing for Master Data Governance (transaction MDGIMG). Go to > General Settings > Configuration Workbench > Select Data Model U1 > Select entity type "MITEM" from Entity Types list > Go to Attributes tab -> Click the "Edit" button > Click the "New" button.






- 3. Add the attributes of Entity Type MITEM as displayed in the following screen.
- 4. Save your settings.

Note: Search help can be added at attribute level if required.



5. Activate the extended Data Model.



6. After activation the following information message is displayed.



7. Make Change Request adjustments after creating the SMT mapping.




Generate MDG Data Model-Specific Structures

In general, if you change a Data Model (for example, if you change attributes of entity types or relationships) you need to regenerate the structures. You can assign a prefix and a package directly in the Data Model. Then the structures are generated automatically with activation of the Data Model.


Older releases: Since the MDG Data Model was changed you need to regenerate the tables. In this Customizing activity, for each Data Model and entity type you generate technical structures and tables in the ABAP Dictionary. The system uses these structures internally for implementing the staging area.

To generate the Data Model-Specific structures use the following steps.

Start Customizing for Master Data Governance (transaction MDGIMG).
Go to > General Settings > Data Modeling > Generate Data Model-Specific Structures.




- 2. Select the row with Data Model U1 > Double-Click Structures in the left-hand panel > Choose the "Generate Selected Structures" button.
- 3. Verify that your structures are successfully generated.




4. In the following steps, you verify that one of the active area mapping structures was successfully generated with new fields.

Start t-code SE11 > Display structure /UGI/_S_U1_PP_MITEM.





You have now verified that the structure /UGI/ S U1 PP MITEM has been generated.



SMT Mapping

You extend mappings by creating new transformations (complex transformations, field mappings) and field checks for them or by editing them.


Important: When the mappings are saved, the system generates the corresponding coding. Make sure that all relevant structures are ready before you start.

SMT Mapping – Get Mapping Names from Data Model U1


Use the following steps to get the mapping names:

- 1. Log into system for cross-client maintenance. Start Customizing for Master Data Governance (transaction MDGIMG).
 - Go to > General Settings > Data Modelling > Generate Data Model Specific Structures > Select Data Model U1 > Double-Click on Mapping.





The SMT mapping names for Entity Type MITEM as displayed.




SMT Mapping - Primary Persistence to Staging

Use the following steps for SMT Mapping from Primary Persistence to Staging area.


1. Log into system for cross-client maintenance. Start Customizing for Master Data Governance (transaction MDGIMG).

Go to > General Settings > Data Modeling > Create and Edit Mappings > Create and Edit Mappings.

Note: For new Entity Types, it is recommended to create a new mapping. When extending existing Entity Types, it is recommended to extend the existing mapping.




2. Extend mapping /UGI/MDG_SMT_MPLAN_ECC2MDG.






3. Select mapping step and choose the "Details" button. Map the fields as displayed in the next screen.



4. Add a mapping step – Assign Source Structure MPLAN_MPOS, assign target structure /UGI/_S_U1_PP_MITEM.




5. Save your changes.

SMT Mapping - Staging to Primary Persistence


Use the following steps for SMT Mapping from Staging area to Primary Persistence.

1. Extend mapping /UGI/MDG_SMT_MPLAN_MDG2ECC.




2. Select mapping step and choose the "Details" button. Map the fields as shown in the following screen.





3. Add a mapping step - Assign Target Structure MPLAN_MPOS and Assign Source Structure /UGI/ S U1 PP MITEM.




4. Save your changes.


Adjust Staging area of Linked Change Requests

Note: This step is necessary to adjust any open Change Requests after you have changed the Data Model.

Start Customizing for Master Data Governance (transaction MDGIMG).
Go to > General Settings > Data Modeling > Edit Data Model > Select Data Model U1 > Double
-Click on Entity Types > Choose the "Adjust staging area of linked Change Requests" button.




2. Choose the "Yes" button.



The following message appears.

Note: Make sure that user DDIC exist in all relevant clients.






Extending the UI Configuration

Add Customization to UI


Use the following steps to add customization to UI.

 Start t-code SE80 > In the drop down select Package > In the input field enter /UGI/MDG_EAM_MNTPLN > Navigate to Web Dynpro > FPM Application Configurations > UGI/USMD_U1_OVP_MPMI.



2. Click the "Start Configurator" button.







In the web browser, click on "Continue in Display Mode".




3. Click on the configuration /UGI/USMD_U1_MPMI_OVP.



4. Select the UIBB where you want to add new attributes and click on Configure UIBB.




5. Click on Additional Functions > Create Customizing.






6. Click on OK.



7. Change your UI. Add new fields that was added in entity MITEM.




Testing the Configuration


Note: If you extend the Data Model per the guidelines shown below, but the fields are not populated when you Activate the Data Model, see SAP Note 1641867 - Values for extension field missing after CR activation

To test your configuration, Go to NWBC > Create/Change Maintenance Plan





Save and Submit the CR. Finalize processing and Approve.



After activation, use t-code SE16 and open table MPOS. Verify attributes that have been transferred correctly.



