
# Creating the Database Manager CLI



Version 7.3



# Copyright

© Copyright 2001 SAP AG.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.1 or any later version published by the Free Software Foundation.

For more information on the GNU Free Documentaton License see http://www.gnu.org/copyleft/fdl.html#SEC4.

# **Icons**

| Icon        | Meaning        |
|-------------|----------------|
| $\triangle$ | Caution        |
|             | Example        |
| <b>→</b>    | Note           |
|             | Recommendation |
| <b>(31)</b> | Syntax         |
|             | Тір            |

# **Contents**

| Copyright                                | 2  |
|--|----|
| lcons                                    |    |
| Content                                  |    |
| Using the Database Manager CLI           | 5  |
| Structure of the Database Manager CLI    | 6  |
| Main Components                          |    |
| Communication Components                 | 6  |
| DBM Server                               |    |
| Creating the Database Manager CLI        | 7  |
| Procedure                                | 7  |
| Link Description File dbmcli.lnk         | 8  |
| Components of the Database Manager CLI   | 9  |
| dbmcli.rc                                |    |
| vcn12.cpp, vcn13.cpp, vcn14.c            |    |
| Link Description cservlib                |    |
| Link Description splib                   |    |
| Link Description eoxlib                  |    |
| Link Descriptions sqlusr, enalib, enblib |    |
| Further Dependencies                     |    |
| Function Check                           | 12 |
| Procedure                                | 12 |
| Result                                   | 12 |

# **Using the Database Manager CLI**

The Database Manager CLI (Database Manager Command Line Interface, DBMCLI) communicates with the DBM server and can, therefore, be used to administrate an SAP DB instance. The behavior of the Database Manager CLI depends on the call parameters and user entries.

Database Manager CLI tasks:

- The Database Manager CLI establishes the connection to the DBM server, and transfers one
  or more commands to it.
- The Database Manager CLI accepts and outputs the DBM server response(s).
- When the Database Manager CLI has been terminated, the connection to the DBM server is released.

# Structure of the Database Manager CLI

The Database Manager CLI consists of the following components:

- Main components
- Communication components
- DBM server

### **Main Components**

Tasks of the main components:

- Accept and evaluate the call parameters and user entries.
- Transfer the DBM server commands to the communication components.
- Receive the DBM server responses from the communication components.
- Evaluate and output the DBM server responses.

## **Communication Components**

Tasks of the communication components:

- Communication with the local DBM server.
- Communication with a DBM server on a remote host.

The communication components are part of the SAP DB runtime environment (RTE).

#### **DBM Server**

A DBM server is integrated in the Database Manager CLI.

If the user requires, this integrated DBM server can be used. In this case, the components required to connect to a separate DBM server are not used.

# **Creating the Database Manager CLI**

The Database Manager CLI is created in the development environment by processing a description file of the lnk file type, namely dbmcli.lnk (\$OWN/sys/desc/dbmcli.lnk). When a description file of the lnk file type is processed, an executable program is created. The link description file dbmcli.lnk also defines where the executable program is stored:

- Windows NT/Windows 2000: The executable program is stored in directory \$OWN\usr\pgm.
- UNIX: The line ->\$INSTROOT/bin/dbmcli is inserted in the link description file dbmcli.lnk. As a result, the executable program is stored in the directory \$OWN/usr/bin.

#### **Procedure**

Enter the following command:

imf dbmcli

This command instructs the development environment to process link description file dbmcli.lnk.

The link description file does not have to be specified with its type (lnk), since its name is unique. The development environment automatically determines the type of the link description file, and, therefore, the type of processing.

The dbmcli (Database Manager CLI) software component is created:

- UNIX: \$OWN/usr/bin/dbmcli
- Windows NT / Windows 2000: \$OWN\usr\pgm\dbmcli.exe

## **Link Description File dbmcli.lnk**

The following extract from link description file dbmcli.lnk contains the main commands required to create the Database Manager CLI. Special commands and switches, which may be needed for the link operation on the individual platforms, have been omitted from this example.

#### Note

To generate the Database Manager CLI, you must always use the complete link description file **dbmcli.lnk** in the source directory.

#### **Explanation of the Link Description File**

The link description file dbmcli.lnk contains references to module files and link descriptions.

References to module files cause these module files to be translated. The translation tools
are assigned on the basis of the file extension of the module files.
 Module files in this example:

```
dbmcli.rc, vcn12.cpp, vcn13.cpp, vcn14.c
```

 References to link descriptions cause these descriptions to be processed in accordance with their description type.

Link descriptions in this example:

```
cservlib, splib, eoxlib, sqlusr, enalib, enblib
```

You can find explanations of the module files and link descriptions in the section *Components of the Database Manager CLI*.

# **Components of the Database Manager CLI**

The Database Manager CLI consists of the following components:

- Module file dbmcli.rc.
- Module file vcn12.cpp.
- Module file vcn13.cpp.
- Module file vcn14.c.
- Link description cservlib
- Link description splib
- Link description eoxlib
- Link description sqlusr
- Link description enalib
- Link description enblib

#### dbmcli.rc

The module file dbmcli.rc is only relevant for Windows NT / Windows 2000. For this reason, the module is encapsulated in a condition in the link description file dbmcli.lnk.

The module file dbmcli.rc is a resource file and is stored in the subdirectory \$OWN\sys\src\Resource. If the module file dbmcli.rc is specified in the link description file dbmcli.lnk, the Resource directory must also be specified explicitly:

#### :Resource/dbmcli.rc

The module file <code>dbmcli.rc</code> contains source code that is specific to Windows NT/Windows 2000. When this file is specified in the link description file, the relevant resources are integrated in the Database Manager CLI.

## vcn12.cpp, vcn13.cpp, vcn14.c

The module files vcn12.cpp, vcn13.cpp, and vcn14.c are stored in the directory \$OWN/sys/src/cn. This directory name is determined implicitly from the module file name. These module files are the main components of the Database Manager CLI, and contain C or C++ source codes.

- The main function is stored in module file vcn12.cpp.
- The module file vcn13.cpp contains certain functions required for file access and character set conversion.
- The module file vcn14.c is used to connect main components with communication components.

#### **Compilation Description**

In the module files vcn12.cpp, vcn13.cpp and vcn14.c, #include instructions are used to refer to include files.

The dependency of a module file on an include file is described in the compilation description. The compilation description appropriate to the module file is determined and evaluated implicitly using the directory in which the module file to be translated is stored.

In addition to the dependency of a module file on an include file, the compilation description specifies further properties of the module files that control how they are translated by the development environment.

#### **Include Files**

The dependencies of a module file on include files is explained in the following example:

#### Example

The dependencies for the module file vcn12.cpp in the directory \$OWN/sys/src/cn are contained in compilation description \$OWN/sys/desc/cn.com. These are described by the following lines in the compilation description:

vcn12.cpp inc=gsp09.h,heo02.h,hcn13.h,hcn14.h,hcn90.h,...

This example only contains the keyword <code>inc</code>. This keyword refers to the required include files. The include files listed after the keyword <code>inc</code> are created by the development environment in include directory <code>\$OWN/wrk/incl</code> before the module file is translated. In doing so, the development environment processes the include files according to their file type. Only type <code>h</code> include files are shown in the example above. Type <code>h</code> include files are copied from the relevant subdirectory under <code>\$OWN/sys/src</code> to a subdirectory of the include directory. The name of this subdirectory is determined implicitly by the development environment from the name of the include file.

## **Link Description cservlib**

The link description cservlib (\$OWN/sys/desc/cservlib.lib) is of the type lib. The link description type lib generates a static library.

A lib type link description consists of several module files that are grouped after translation to form the appropriate library. The dependencies and properties of the individual module files are stored in the directory-specific compilation descriptions.

If cservlib is entered in link description file dbmcli.lnk, the cservlib library is integrated in the Database Manager CLI.

The cservlib library contains the functionality of the DBM server integrated in the Database Manager CLI.

## **Link Description splib**

The link description **splib** (\$OWN/sys/desc/splib.lib) is of the type **lib**. The splib library contains modules with functions that can be used generally.

## **Link Description eoxlib**

The link description **eoxlib** (\$OWN/sys/desc/eoxlib.lib) is of the type **lib**. The eoxlib library contains communication components of the SAP DB runtime environment.

## Link Descriptions sqlusr, enalib, enblib

The link descriptions sqlusr, enalib, enblib (\$OWN/sys/desc/sqlusr.lib, \$OWN/sys/desc/enalib.lib, \$OWN/sys/desc/enblib.lib) are of the type lib.

The sqlusr, enalib, enblib libraries contain communication components of the SAP DB runtime environment. Since the SAP DB runtime environment is platform specific, different libraries are used on Windows NT/Windows 2000 and UNIX. For this reason, the link description file is encapsulated in a condition in the link description file dbmcli.lnk.

## **Further Dependencies**

If you are using  $\bar{W}$  indows NT or Windows 2000, note that the Database Manager CLI requires a dynamic library. This library must be created explicitly.

To do so, enter the following command: imf sqltcp

## **Function Check**

You can check the function of the Database Manager CLI by executing a DBM server command.

#### **Procedure**

1. Check whether you can actually access the software component you have just created, the Database Manager CLI (\$OWN/usr/bin/dbmcli, Windows NT/Windows 2000: \$OWN\usr\pgm\dbmcli.exe).

2. Enter the DBM server command dbm\_version:

```
dbmcli [-n <server_node>] -d <database_name> -u
<dbm_userid>,<dbm_password> dbm_version
```

#### **Example**

```
dbmcli -d TST -u dbm,dbm dbm_version
```

#### Result

The output should roughly be as follows:

OK

VERSION = 7.2.4

BUILD = DBMServer 7.2.4 Build 009-000-220-192

OS = UNIX

INSTROOT = /usr/sapdb-srv

LOGON = False CODE = ASCII SWAP = full