USER GUIDE

IBM i 5250 Terminal Emulator for Development Support (with MCP Server support)

IBM 5250 MCP

User Guide

IBM 5250 MCP Project

Edition 0.1 (v0.1.17-beta)
November 2026

Important Safety Information

Before using this product, be sure to read this "Important Safety Information" carefully and use the product correctly.

Caution	Incorrect handling may affect business data or resources on the IBM i.
Prohibited	Operations that must never be performed.
Note	Useful tips and reference information.

⚠ Confirm Your Operations

This software communicates with IBM i (formerly AS/400, iSeries). Before running any operation that may unintentionally change data on the server (for example, delete commands or system value updates), always confirm its content.

⊘ About Passwords

Do not leave the device or share the screen while a password is entered on screen. Handle passwords in accordance with your organization's operational rules.

i About the Screen Examples in This Guide

The screens shown in this guide were captured in a test environment. The display may differ from your own environment.

Contents

1. Introduction 1

1.1 Product Overview 2

1.2 Structure of This Guide 2

2. Names of Parts 3

2.1 The Whole Screen 4

2.2 Toolbar Description 5

2.3 Operator Information Area (OIA) 7

2.4 Exclusive and Shared Input 8

3. Before You Begin 9

3.1 Starting a Connection 10

3.2 Signing On 11

4. Basic Operations 13

4.1 Entering Text 14

4.2 Function Keys 15

4.3 Copy and Paste 16

4.4 Mouse Operations 17

5. Useful Features 18

5.1 AUTOTYP (Automatic Input) 19

5.2 Automatic Execution After Connecting 20

5.3 Recording Operations 20

5.4 Display Switching 20

5.5 Voice Input 21

5.6 Online Help 22

6. Troubleshooting 23

6.1 Cannot Connect 24

6.2 The Screen Does Not Respond 24

6.3 Other 25

7. Glossary 26

8. Keyboard Reference 29

Chapter 1

Introduction

Introduces the product overview and how to read this guide.

1 Introduction

1.1 Product Overview

IBM 5250 MCP is development-support software for operating, in a web browser, 5250 terminal screens that run on IBM i (formerly AS/400, iSeries). It also works as a Model Context Protocol (MCP) server, supporting automated operation by generative AI agents (such as Claude).

1. **Operate in a web browser** No dedicated client needs to be installed. You can operate 5250 screens from your own web browser.
2. **Japanese display support** Correctly displays screens that mix DBCS (double-byte characters) and SBCS (single-byte characters).
3. **Automatic input feature** You can save a frequently performed sequence of operations as an "AUTOTYP script" and reproduce it with a single click.
4. **MCP server support** Generative AI agents can invoke and automatically operate 5250 screens. This is useful for test automation and for embedding into operational batch processing.

> *i* **Supported IBM i Versions**
>
> This product implements the TN5250E protocol (compliant with RFC 4777 / RFC 1205). You can use it without any special configuration on a typical IBM i 7.x system.

1.2 Structure of This Guide

Chapter	Main Content
Chapter 1	Introduces the product overview and the structure of this guide.
Chapter 2	Explains the names and roles of the parts of the screen.
Chapter 3	Explains the procedure for starting a connection and signing on.
Chapter 4	Explains basic operations such as entering text, function keys, and copy and paste.
Chapter 5	Explains useful features such as AUTOTYP, operation recording, and display switching.
Chapter 6	Guides you through what to check when something is not working correctly.
Chapter 7	Explains the technical terms used in this guide.
Chapter 8	A list of keyboard shortcuts.

> *i* **For Administrators**
>
> For administrator-oriented content such as creating connection configurations, developing AUTOTYP scripts, and handling print spools, please refer to the separate "IBM 5250 MCP Administrator Guide".

Chapter 2


Names of Parts

Explains the names and roles of the parts of the screen.

2 Names of Parts

2.1 The Whole Screen

The screen of this product consists of the following three areas. Check the numbers ①–③ and their corresponding positions on the screen.



1 **Toolbar** There are two toolbar rows, upper and lower. On the left, the first row contains connection management, configuration editing, and saving settings, and the second row contains the display font and size settings. On the right, the first row contains display and other switches, and the second row contains the keyboard input target and other buttons (mouse wheel settings, hide toolbars, help, etc.). Function keys and AUTOTYP operation buttons are also placed around the screen.

2 **5250 Screen** Displays the screen sent from IBM i. The "input fields" for entering text are also shown here.

3 **Operator Information Area (OIA)** Displays the keyboard input state, cursor position, communication state, and so on. For details, see section 2.3.

2.2 Toolbar Description




Figure 2.2-1 Upper Toolbar

Each button is described below (the left column shows the actual button appearance).

Button	Description
First Row — Connection / Configuration	
Disconnect	**Disconnect / Connect**. Disconnects the current session. While disconnected, the button changes to Connect. When connecting, the connection begins in the current window; no new window is opened.
New	**New**. Opens a new, unconnected window. Use this when you want to use multiple 5250 sessions at the same time.
Dup	**Duplicate**. Opens a new window using the same connection configuration as the current session (the connection is also made immediately). When not connected, this behaves the same as "New" and opens an unconnected window.
Manage	**Manage**. Displays a dialog for adding, editing, and deleting connection destination configurations. The default display font and size can also be specified for each configuration.
Save	**Save**. Saves the current display font, size, bold, italic, and other settings to the connected configuration. The next time you connect with the same configuration, those settings are restored.
First Row (right) — Switches (the three on/off buttons show a dimmed icon while off)	
US	**Language**. Switches the display language of the viewer UI (Japanese / English). The button shows the current language (JP / US). Switching it also changes the default font and default host code page used when creating a new connection configuration (Japanese: MS Gothic / cp1399, English: Consolas / cp037). Already-saved configurations are not affected.
	**Column separator**. Switches the column separator display between "lines" and "dots".
A	**A / ｱ**. Switches the SBCS code page (DBCS sessions only). A = lowercase Latin (cp1027), ｱ = Katakana (cp290)
	**Window mode toggle**. Switches the viewer window between an "app window" (a dedicated window without an address bar) and a normal browser window. The button shows the current mode (= app window / = normal window). Clicking it closes the current window, reopens it in the other mode, and also changes the default for the next startup.
	**Exclusive / Shared**. Switches the input mode. **Exclusive** (the default at startup) means that even if the same connection is opened in another browser or PC, only the one person holding exclusive control can enter input. With **Shared**, everyone can enter input, and multiple people can operate at the same time. While someone holds exclusive control, other browsers cannot switch to exclusive (the button appears disabled). For details, see section 2.4.
	**Input highlight**. Toggles the yellow highlighting of input fields (on / off).
	**Vertical "0E 0F"**. Shows or hides shift characters (SO/SI) (DBCS sessions only).
	**Blink display**. Turns blinking on or off for 5250 display attributes 2A, 2B and 2E (red, blinking). **Blinking is on by default** (IBM i Access Client Solutions does not blink by default; turn this off for the same display). Only these three attributes, which the IBM manual defines as blinking, blink. The setting is saved per browser.
Second Row — Display Font	
Font selection	Selects the display font for the 5250 screen. At the top of the list are monospace fonts (recommended), and below them all the fonts installed on the OS are listed. In

	Japanese (DBCS) sessions, a Japanese font that can correctly display kanji is selected by default.
− / **Size** / +	Changes the font size. In automatic mode, the size currently in use is shown (cannot be changed); in fixed mode, you can enter a value directly. − / + increase or decrease by 1 px at a time.
AA Auto	**Auto** / **Fixed**. Switches the size adjustment method. **Auto** automatically adjusts the size to fit the 5250 screen within the window. **Fixed** locks the size to the specified value and adjusts the window size so that the 5250 screen fits exactly.
B	**Bold (B)**. Toggles bold display on / off.
I	**Italic (I)**. Toggles italic display on / off.
Second Row (right) — Keyboard input target (5250 screen = teal / toolbar = dark red)	
	Keyboard input target. Switches the keyboard input target between the 5250 screen (on) and toolbar operations (off). You can also switch with Ctrl + K.
Second Row (right) — Other (open / run)	
	Wheel settings. Opens a settings dialog for screen scrolling with the mouse wheel.
	Microphone. Click to start voice input; it stops automatically when you finish speaking (click again while recording to stop midway). For details, see section 5.5.
	Hide all toolbars. Hides all toolbars (the two upper toolbar rows, the notification area, and the function key toolbar) and displays only the 5250 screen (the OIA remains). This is a **hide-only** button. To show them again, click the gray area outside the 5250 screen (because the button itself also disappears while hidden). When hidden, the keyboard input target switches to the 5250 screen (Keyboard on), and the 5250 screen font size is readjusted to fit the freed-up area. You can specify the initial state per connection configuration ("Toolbar initially hidden" in the Manage dialog), and it is applied when connecting.
	Help (i). Opens the help in a normal browser window. It shows the product version and build date, the End-User License Agreement (EULA), third-party notices, this User Guide, and the Admin Guide. For details, see section 5.6.

> ***i*** **About the Default Values of the Display Switching Buttons**
>
> For the four display switches "Input highlight", "Column separator", "A / 𝔄", and "{ } / · ·", the default values are saved as a single set for the entire viewer (= not per connection configuration). Once set, they are retained even after reloading the browser.

2.3 Operator Information Area (OIA)

The status line at the bottom edge of the 5250 screen (the Operator Information Area, abbreviated as **OIA**) displays the current keyboard state and communication state.



Figure 2.3-1 Close-up of the Operator Information Area (OIA)

Display	Meaning
MA* (column 1)	Indicates that you are connected to IBM i.
X II (column 9)	The keyboard is temporarily locked. This product is processing the previous operation (such as printing). You can release it with the RESET key.
X SYSTEM (column 9)	Waiting for a response from the server. Please wait a moment.
COMM659 (column 19)	Communication has been disconnected. The session tries to reconnect automatically (**COMM657** = establishing the connection, while trying). It disappears automatically when communication is restored.
Alphanumeric / **Kana** (column 26)	Indicates the current input mode (DBCS sessions only).
A (column 43)	Indicates that Caps Lock is on.
^ (column 52)	Indicates insert mode. It appears whenever insert mode is on.
18/007 (column 75)	Indicates the current cursor position (row 18 / column 7). It is shown as a combination of a 2-digit row and a 3-digit column.

> **Cursor Display in Insert Mode**
>
> In insert mode, the cursor changes from a "tall block (overwrite mode)" to a "lower-half block (insert mode)". Pressing the Insert key toggles it (on / off), and the RESET key also returns it to overwrite mode (this is not a toggle; it only releases insert mode).
> In insert mode, "^" also appears at OIA column 52.

2.4 Exclusive and Shared Input

You can open the same connection in multiple browsers or PCs at the same time. In this case, the "input mode" controls who can enter input. Switch with the 👤 / 👥 button on the toolbar (in either mode, everyone who has it open can view the screen).

Mode	Description
👤 **Exclusive** (default at startup)	Only the one person holding exclusive control can enter input. Even if the same connection is opened in another browser or PC, others cannot enter text, send keys, or move the cursor.
👥 **Shared**	Everyone who has the connection open can enter input. Use this when you want multiple people to operate at the same time. Input is processed in the order it arrives.

> While someone holds exclusive control, the 👤 button in other browsers appears disabled and cannot be switched to exclusive. When the person who held exclusive control switches to 👥 Shared or closes the connection, another browser becomes able to take exclusive control.

Chapter 3

Before You Begin

Explains the procedure for starting a connection and signing on.

3 Before You Begin

3.1 Starting a Connection

The procedure for starting a connection is as follows.

1 Open the product screen in your browser

Open the address provided in advance by your administrator (for example, `http://localhost:5250/`) in a web browser. If you started the product directly, an unconnected screen opens automatically.

> **When using an AI agent (MCP)**
>
> If you asked an AI agent such as Claude to connect, this step is not needed. When the connection completes, a window showing that session opens automatically (one connection = one window).

2 Select a connection configuration

From the "-- Select configuration --" drop-down at the top of the toolbar, select the connection destination you want to use. Selecting it starts the connection immediately.

> **If the Connection Configuration Is Not in the List**
>
> If the connection destination you want is not in the list, contact your administrator. Alternatively, you can add a new one from the "⚙ Manage configurations" button (for details, see the "Administrator Guide").

3 The sign-on screen appears

When the connection succeeds, the IBM i sign-on screen appears.




Figure 3.1-1 Sign-on Screen

3.2 Signing On

1 Enter your user name

Enter your user name (the value provided by your administrator) in the "User" field.

2 Move to the password field

Press the Tab key to move the cursor to the "Password" field.

3 Enter your password and press the Enter key

After entering your password, press the `Enter` key. When sign-on succeeds, the IBM i menu screen (or command entry screen) appears.




Figure 3.2-1 Command Entry Screen After Sign-on

> ⚠ **When Sign-on Fails**
>
> Confirm that the user name and password are correct. The account may also be disabled on the IBM i side. If you still cannot sign on after several attempts, contact your administrator.

Chapter 4

Basic Operations

Explains entering text, function keys, copy and paste, and more.

4 Basic Operations

4.1 Entering Text

You can enter text from the keyboard at the position where the cursor is blinking (= an input field).

1 Select an input field

Click the position where you want to enter text with the mouse, or use the Tab key to move to the next field. To move in the reverse direction, press Shift + Tab. Depending on the application screen design, the destination may be a field designated by the screen rather than the next one in on-screen order (the same behavior as a real 5250 terminal).

2 Enter text

Enter text from the keyboard. Japanese input (IME) can also be used.

3 Press a confirm key

Pressing the Enter key, or the appropriate F1–F24 key, sends the entered content to IBM i.

> **Keys Useful for Editing**
>
> - **BackSpace**: Moves the cursor one character to the left (the character is not deleted).
> - **Delete**: Deletes the character at the cursor position and shifts the text to the right leftward.
> - **Insert**: Switches between insert mode (= inserting characters in between) and overwrite mode. In insert mode, "^" appears at OIA column 52.
> - **End**: Erases from the cursor position to the end of the line (Erase EOF).

> **About Japanese (DBCS) Input Fields**
>
> In a field for entering double-byte characters (kanji and kana), the mode automatically switches to "Kana" when the cursor enters (shown in the OIA). The characters that can be entered are determined by the type of field, and if you enter a character that does not match the type, a message appears at the bottom of the screen and the input is rejected.
>
> - **Double-byte-only field**: If you enter alphanumeric characters, "DBCS is required as input." appears.
> - **Either-or field**: If the first character entered is alphanumeric, that field becomes alphanumeric-only; if it is a double-byte character, it becomes double-byte-only (mixing is not allowed).

Field Input Rules and Pre-send Checks

Fields may have input rules defined by the screen design. Characters that do not match the rules are rejected as you type. Checks also run when you press a confirm key and when you leave a field with Field Exit (Right Ctrl); if a rule is not satisfied, nothing is sent (or the cursor does not leave the field) — the same behavior as a real 5250 terminal. In either case a message appears at the bottom of the screen. The message disappears when you move the cursor with the arrow keys. (Messages are displayed in Japanese; the equivalents are shown below.)

Message (equivalent)	Meaning and action
Only characters 0 through 9 are allowed.	Digits-only field. Enter digits only.
Only numeric characters are allowed in this field.	Numeric field. Only digits, the symbols (comma, period, +, −), and blanks can be entered.
Only alphabetic characters are allowed in this field.	Alphabetic-only field. Only letters, the symbols (comma, period, −), and blanks can be entered.
Mandatory-fill field. You must enter data to the end of the field.	Fill the field to the last position before pressing a confirm key.
Mandatory-entry field. You must enter data.	The cursor moves to the required field; enter data and press the confirm key again.
Check-digit error.	A number with a check digit (such as an account number) is incorrect. Verify the number and enter it again.
The Enter key is not allowed in this field.	A right-adjust field has pending input. Press Right Ctrl (Field Exit) to complete the field, then press the confirm key.
The Dup key or Field Mark key cannot be used in this field.	The DUP key cannot be used in this field.

4.2 Function Keys (F1–F24)

In 5250 applications, the F1–F24 function keys are used frequently. The common assignments are as follows.

Key	Function (common example)
F1	Displays help.
F3	Ends the current process.
F4	Displays a list of choices (prompt).
F5	Refreshes the screen to the latest state.
F12	Cancels the process and returns to the previous screen.




Figure 4.2-1 Example of function key descriptions shown at the bottom of the screen

How to Enter F13–F24

`F13`–`F24` can also be entered with `Shift` + `F1`–`F12`. They can also be operated as on-screen buttons from the **▼ More** button at the bottom.

4.3 Copy and Paste

1 Select a range

Dragging the mouse highlights the range you want to copy in yellow (just drag—you do not need to hold `Ctrl` or `Shift`).

You can also select with the keyboard. Hold `Shift` and move the cursor with the arrow keys (`↑` `↓` `←` `→`) to highlight the range you pass over.

2 Copy

Pressing `Ctrl` + `C` copies the selected range to the clipboard.

3 Paste

Place the cursor in an input field and press `Ctrl` + `V`. Multi-line text with line breaks is also pasted automatically according to the arrangement of the fields.

4 Undo the paste (optional)

Pressing `Ctrl` + `Z` immediately after pasting restores the state before the paste. You can undo only immediately after pasting; you cannot undo after pressing another key.

> **When the Paste Does Not Fit in the Field**
>
> If the text being pasted exceeds the number of columns in the field, it is flowed into the input lines below, aligned to the column at the cursor position (block paste).

> **Paste Caution**
>
> When pasting a password from the clipboard into a password field, always clear the clipboard after pasting.

4.4 Mouse Operations

When you click on the 5250 screen with the mouse, the cursor moves to that position. The following operations are also supported.

Operation	Behavior
Click a normal position	The cursor moves to that position (nothing is sent to the server).
Click a choice or push button	You can directly click on-screen choice buttons or push buttons (supporting the DDS MOUBTN keyword) to select or execute them.
Click a URL (underlined)	Opens a URL shown on the screen (http / https / www / mailto / ftp / file / gopher) in a new window (same as the URL hotspots of IBM i Access Client Solutions; URLs inside input fields are excluded). Browsers cannot open `file://` URLs (for example `FILE://SERVER/SHARE/A.JPG`) directly, so the MCP server reads the file from the PC through UNC (`\\SERVER\SHARE\A.JPG`) and returns it (only for URLs shown on the screen). Beforehand, make sure you can access the folder, for example by opening it in Explorer.
Drag	Selects a range (for copying; see section 4.3).
Click the scroll bar arrows (▲ / ▼)	Scrolls one line at a time.
Click the scroll bar track (other than the arrows)	Scrolls one page at a time.

Chapter 5

Useful Features

Introduces various features that streamline your daily work.

5 Useful Features

5.1 AUTOTYP (Automatic Input)

AUTOTYP is a mechanism that automatically runs a frequently performed sequence of inputs all at once. For example, you can reproduce everything from "signing on to opening a menu" with a single click.

The AUTOTYP operation buttons are located in the lower panel that appears when you click the **▼ More** button at the right end of the toolbar at the bottom of the screen (while the panel is shown, the button changes to **▲ Less**; clicking it again collapses the panel).



Figure 5.1-1 Lower panel shown by ▼ More (the group on the right contains the AUTOTYP operation buttons)

The AUTOTYP operation buttons are described below (the left column of the table shows the actual appearance of each button).

Button	Description
-- autotyp --	**Script selection**. Choose the script to run or edit from the list of AUTOTYP scripts in the scripts folder.
• Rec	**Rec (record)**. Starts recording your screen operations. While recording, the button turns red; clicking it again stops recording and opens the edit dialog (see Section 5.3).
▶ Run	**Run**. Runs the selected script on the current screen.
⏸ Pause	**Pause**. Pauses the running script. Clicking it again resumes from the same position (enabled only while a script is running).
■ Stop	**Stop**. Aborts the running script. It cannot be resumed (enabled only while a script is running).
✎ Edit	**Edit**. Opens the selected script in the edit dialog, where you can review, modify, and save its contents.

1 Select a script

From the "-- autotyp --" drop-down in the lower panel shown by ▼ More, select the script you want to run.

2 Run it

Clicking the **▶ Run** button runs the selected script on the current screen.

3 Operate as needed

Choose one of the following three options during execution.

- **Just wait**: Please wait for the script to finish.
- **Pause**: Click ⏸ **Pause**. Clicking it again resumes from the same position.
- **Stop**: Click ■ **Stop**. Execution is aborted. It cannot be resumed.

> ⚠ **About Input While AUTOTYP Is Running**
>
> While AUTOTYP is running, keyboard and mouse input to the 5250 screen is temporarily disabled. To enter input, first perform the "Pause" or "Stop" described above, and then operate.

5.2 Automatic Execution After Connecting

If you set up a "post-connection automatic-execution AUTOTYP" for each connection configuration, simply connecting can automatically perform everything from signing on to displaying the menu. For how to set this up, see the "Administrator Guide".

5.3 Recording Operations

You can automatically record keyboard and mouse operations as an AUTOTYP script.

1 Start recording

Click the ● **Rec** button. The button turns red to indicate that recording is in progress.

2 Perform the operations to record

Perform the operations you want to save as AUTOTYP, such as key input, function keys, and pasting.

3 Stop recording

Clicking the ● **Rec** button again stops recording and opens the edit dialog. Review the content, modify it as needed, and then save.

5.4 Display Switching

You can change the screen display to your preference using the toolbar icons.

Icon	Function
Four-pointed star icon	Highlights input fields in yellow. You can see at a glance where input is possible (on / off). The star is filled while it is on.
Three vertical lines / dashed line icon	Switches whether column separators are shown as vertical lines or as dotted lines. The icon shows three vertical lines while lines are shown, and a dashed line while dots are shown.
A / ｱ	Switches the SBCS display characters toward lowercase Latin or toward Katakana (DBCS sessions only).
Vertical "0E 0F"	Shows or hides shift characters (SO/SI) (DBCS sessions only). The button is bright while they are shown.
Light bulb icon	Turns blinking on or off for text with display attributes 2A, 2B and 2E (red, blinking). **Blinking is on by default**. IBM i Access Client Solutions does not blink by default (it can be enabled in its settings), so turn this off for the same display. The setting is saved per browser.

The above four display switches are saved as a single set of default values for the entire viewer (= not per connection configuration). The settings are retained even after reloading the browser.

5.5 Voice Input

Using the microphone button on the toolbar, you can convert what you say into the microphone into text and send it as input to Claude. You can convey screen operations and instructions by voice, without using the keyboard.

The speech recognition language follows the viewer's display language: it recognizes Japanese (ja-JP) when the display language is Japanese, and English (en-US) when it is English (switched with the language button).

> **Before Using Voice Input**
>
> Voice input is available only when you use this viewer together with the **Claude extension** in **Visual Studio Code**. In addition, you need to **add a hook** to pass the voice to Claude. For the setup procedure, see the separate "Administrator Guide".

1 Start voice input

Click the microphone button. The button changes state and the microphone becomes active (the first time, the browser asks for permission to use the microphone).

2 Speak

Speak what you want to enter. What you say is converted into text.

3 Sent to Claude

The converted text is sent as input to Claude. Voice input ends automatically when you finish speaking (to stop it midway, click the microphone button again).

5.6 Online Help

Click the **Help** (ⓘ) button on the second toolbar row to open the help in a normal browser window. The first page shows the following information.

Item	Description
Version	The product version and build date. Please include them when contacting support.
License	Shows the End-User License Agreement (EULA) and the third-party notices for open-source software included in the product.
Help	Shows the User Guide (this document) and the Admin Guide.

When you open a guide, the screen is divided into two panes.

Pane	Description
Left — contents and search	Contains the document selector, the table of contents, and a search box. Clicking an entry in the table of contents scrolls the right pane to that heading. Typing two or more characters in the search box lists the matching places in the text; clicking one jumps to it and highlights the matched words.
Right — document	The body of the selected document, including images.

> ***i*** **Help display language**
>
> The help opens in the viewer's display language (the language toggle button): the Japanese guides when set to JA, and the English guides when set to US.

Chapter 6

Troubleshooting

Guides you through frequently asked questions and how to check them.

6 Troubleshooting

6.1 Cannot Connect

Symptom	Please Check
The screen does not appear even after selecting a connection	• Check with your administrator whether IBM i is running. • Check the state of the network (LAN cable, Wi-Fi, VPN). • Reload the browser (`Ctrl` + `R`) and then try again.
COMM659 appears in the OIA	Communication has been disconnected. As in ACS, the session starts trying to reconnect automatically after 1 second (**COMM657** while trying) and returns to the sign-on screen when connected. If it is not restored within the set number of attempts (default: 10, every 5 seconds), COMM659 remains; click "🔌 Connect" on the toolbar to reconnect.




Figure 6.1-1 COMM659 display when disconnected

6.2 The Screen Does Not Respond

Symptom	Please Check
No response when pressing keys / **X II** appears in the OIA	This product is processing the previous operation (such as printing). Pressing the `RESET` key releases it.
X SYSTEM stays displayed in the OIA	The server is being awaited for a response. Normally just wait a moment. If no response returns for a long time, press `SysReq` (System Request), type **2** on the displayed input line, and press `Enter` to force-end the program or command running on the IBM i. If that still does not resolve it, consult your administrator.




Figure 6.2-1 Example of X II appearing right after the print key (printing in progress)

6.3 Other

Symptom	Please Check
The characters are too small to see	Use the + button in the second toolbar row to increase the font size. Setting it to "**Aa Auto**" automatically adjusts the size to fit the window.
Keyboard input is not reflected on the 5250 screen	It is set to KBD OFF. Click the **KBD OFF** button or press `Ctrl` + `K` to turn it back ON.
Cannot enter Japanese	Check that the IME is enabled. Check whether the OIA display is stuck on "Alphanumeric".
Pressing a confirm key does not send anything, and a message appears at the bottom of the screen	A field input rule (mandatory fill, mandatory entry, etc.) is not satisfied. Correct the input as the message indicates (see Section 4.1 "Field Input Rules and Pre-send Checks"). The message disappears when you move the cursor with the arrow keys.

Chapter 7

Glossary

Explains the technical terms used in this guide.

7 Glossary

IBM i

An operating system for core enterprise systems provided by IBM. It was formerly called AS/400 and iSeries.

5250

The name of the terminal protocol used for communication with IBM i. This product implements TN5250E (5250 over Telnet).

Sign-on

Refers to logging in to IBM i by entering a user name and password.

Function key

Keys such as `F1`–`F12` in the top row of the keyboard. In 5250 applications, `F1`–`F24` are used.

OIA (Operator Information Area)

An abbreviation for Operator Information Area. Refers to the status line displayed at the bottom edge of the screen, showing the keyboard state and so on.

X II / X SYSTEM

OIA displays indicating that the keyboard is locked. X II indicates that this product is performing processing, and X SYSTEM indicates that it is waiting for a response from the server.

COMM659

An OIA display indicating that communication has been disconnected. The session tries to reconnect automatically, and the display disappears when communication is restored.

COMM657

An OIA display indicating that the connection to the host is being established (while an automatic reconnection is being tried).

Insert mode

A mode in which entered characters are inserted in between at the cursor position. Switch it with the `Insert` key. In insert mode, "^" appears at OIA column 52.

AUTOTYP

This product's own mechanism for automatically running a previously recorded sequence of input operations.

MCP (Model Context Protocol)

A communication protocol for invoking external tools from generative AI agents such as Claude. This product works as an MCP server, allowing AI agents to automatically operate 5250 screens.

Connection configuration

A setting that bundles together the host name, port number, code page, and so on of a connection destination. You can switch between and use multiple connection destinations.

DBCS / SBCS

DBCS refers to double-byte characters (kanji, hiragana, katakana, etc.), and SBCS refers to single-byte characters (alphanumerics, half-width katakana, etc.).

Chapter 8

Keyboard Reference

A list of the keyboard shortcuts available in this product.

8 Keyboard Reference

8.1 Basic Operation Keys

Key	Function
Enter	Sends the entered content.
Tab	Moves to the next input field.
Shift + Tab	Moves to the previous input field.
Home	Moves to the first input field.
← → ↑ ↓	Moves the cursor up, down, left, and right.
BackSpace	Moves the cursor one character to the left (does not delete the character).
Delete	Deletes the character at the cursor position and shifts the text to the right leftward.
Insert	Switches between insert mode and overwrite mode (on / off).
End	Erases from the cursor position to the end of the line (Erase EOF).
Esc	Used for closing dialogs, sending the ATTN key, and so on.

8.2 Function Keys

Key	Function
F1 – F12	Sent as F1–F12 as is.
Shift + F1 – F12	Sent as F13–F24.

8.3 Clipboard Operations

Key	Function
Ctrl + C	Copies the selected range to the clipboard.
Ctrl + V	Pastes the contents of the clipboard.
Ctrl + Z	Pressing this immediately after pasting undoes the paste.
Mouse drag	Selects a range (no modifier key needed).
Shift + arrow keys	Moves the cursor to select a range (a selection method that does not use the mouse).

8.4 Special Operations

Key	Function
Ctrl + K	Switches the keyboard input target (KBD ON / OFF).
Ctrl + F3	Character switch. Toggles the display between half-width katakana and lowercase letters (same as A / ｱ on the toolbar; DBCS sessions only), like the same key in IBM i Access Client Solutions. Use it when a lowercase URL is shown in katakana.
Left Ctrl (alone)	Sends the RESET key.
Right Ctrl (alone)	Sends Field Exit.

IBM 5250 MCP User Guide

IBM 5250 MCP Project

Edition 0.1 (v0.1.17-beta) Published November 2026

For inquiries, contact your in-house systems staff