Build the Size Class File in Copilot (P11)

From the PowerPoint slide to the workbook Config `SizeClassFile` points at

Instructions. Do this first: it is the most important Copilot prompt. The macro builds nothing without a size class file, and a model missing from it lands in UNMAPPED. The slide has the latest classes, but not in the macro's layout or MODEL_GROUP spelling. Run Steps 1 to 3 **in one Copilot chat**, in order, attaching the file each one names; Step 4 is optional. Paste each boxed prompt as it is; where it shows <TAB>, a tab is meant. If Copilot loses the earlier table, start a new chat and paste it under the prompt.

Step 1. Read the slide (attach the PowerPoint file)

```
Attached is a PowerPoint file. One slide in it lists Bobcat machine models and the size class
   each belongs to. The layout may be a table, groups of models under class headings, or
   columns per class.

Task: build one table with one row per machine model on that slide.

How to fill each row:
- Name of machine: the model code only, as written on the slide, without the word Bobcat or
   the machine type. Examples: T76, S650, E35, T76-2, E50Z. If the slide writes a series as a
   suffix (for example "T76 R2" or "T76 R-Series"), keep it exactly as written; Step 2 fixes the
   spelling.
- Slide class: the class label exactly as the slide shows it for that model.
- Size Class: the slide class translated to exactly one of these names, nothing else:
  Track loaders (T...), by rated operating capacity in lb, as the business defines them:
    0<2000, 2000<2300, 2300<2600, 2600<3000, 3000<3500, 3500&Over
  Mini excavators (E...), by nominal tonnes, as the business defines them:
    >00-01, >01-02, >02-03, >03-04, >04-05, >05-06, >06-10
  Skid-steer loaders (S...), by frame size, kept exactly as the slide names them:
    EX Small, Small Frame, Med Frame, Large Frame
- Rated Operating Capacity: the capacity in lb if the slide shows it (for an excavator, its
   operating weight in lb if shown); otherwise leave it blank.
- HP: the horsepower if the slide shows it; otherwise leave it blank.
- Notes: write "CHECK: slide class does not match" if the slide label does not translate to
   exactly one of the names above (for example its range crosses a boundary), "CHECK: on a
   class boundary" if a capacity shown is within 100 lb of a track loader class edge, and
   "CHECK: listed twice" if a model appears more than once on the slide. Otherwise leave it
   blank.

Rules:
- Use only what is on the slide. Do not add models from memory. Do not look anything up.
- Do not explain. Reply only in the format below.
- If you cannot find such a slide, reply with one line: CANNOT: <reason>

Reply in exactly this format:
SLIDE: <slide number and title>
CLASS LABELS
<slide class label> -> <Size Class name, or NONE>
TABLE
Name of machine | Slide class | Size Class | Rated Operating Capacity | HP | Notes
<one line per model>
MODELS ON SLIDE: <number>
```

Check. Count the models on the slide and compare with MODELS ON SLIDE. Each CLASS LABELS line must point to the class you expect; if not, correct Copilot in the chat (e.g. `"Under 2,000" is 0<2000`) and ask it to redo the table.

Step 2. Check against Order Intake (attach it)

```
Attached is the Order Intake export. Use its first sheet. Keep the table from the slide.

Task: compare the slide table with the models in this export.
1. Take the export rows whose PRODUCT_TYPE_ABBR is CTL, MX or SSL (ignore capitals
   and extra spaces). List every different MODEL_GROUP among them.
2. For each MODEL_GROUP, find its row in the slide table: the same name ignoring capitals
   and spaces, or the same model written another way (for example "T76 R2" on the slide and
   "T76-2" in the export). When it is the same model written another way, change Name of
   machine in the slide table to the export's spelling and add "renamed from <slide name>" to
   Notes.
3. A MODEL_GROUP with no row in the slide table: add a row with Name of machine = the
   MODEL_GROUP exactly as in the export.
   - E followed by digits (a mini excavator): leave Size Class blank; Notes "CHECK: not on slide,
     class unknown". There is no rule for it: the class comes from the slide or the spec sheet.
   - Any other model: give your best Size Class only if you are sure of its rated operating
     capacity; Notes "CHECK: not on slide". If you are not sure, leave Size Class blank and
     write "CHECK: not on slide, class unknown".
4. Keep every slide row, including models the export does not have.

Rules:
- Read every row of the export. Do not explain. Reply only in the format below.
- If a column is missing or you cannot read the file, reply with one line: CANNOT: <reason>

Reply in exactly this format:
RENAMED
<slide name> -> <MODEL_GROUP>
ADDED (not on slide)
<PRODUCT_TYPE_ABBR> | <MODEL_GROUP> | <rows in export> | <Size Class or
   blank>
ON SLIDE, NOT IN EXPORT
<Name of machine>
TOTAL MODEL_GROUPS IN EXPORT: <number>
```

Check. Every blank Size Class needs one before Step 3: find the capacity on the spec sheet and tell Copilot, e.g. `T870 is 3500&Over`. A model left blank stays UNMAPPED.

Step 3. The finished table (same chat)

```
Now give the final size class table: the slide table after Step 2, with the corrections I gave you in
   this chat.

Rules:
- One row per Name of machine. No blank Size Class. Size Class must be exactly one of the 17
   names from Step 1.
- Sort: track loaders (T...), then skid-steer loaders (S...), then mini excavators (E...), then
   anything else; inside each group by Size Class in the order listed in Step 1, then by Name of
   machine.
- Reply only with the table as tab-separated text, no other words, starting with this header row:
Name of machine <TAB> Rated Operating Capacity <TAB> HP <TAB> Size Class <TAB>
   Notes
- After the table, one line: ROWS: <number of model rows>
```

If your Copilot can create files, ask instead: *Create an Excel workbook with this table on the first sheet, named Size Class, and Size Class formatted as text*; then go to step (d).

(a) Open a new workbook; set column D (Size Class) to *Home > Number Format > Text* before pasting.

(b) Paste into cell A1 of the **first sheet** (the macro reads only that one).

(c) Check that ROWS matches the rows pasted and no Size Class cell is empty.

(d) Save it as a local `.xlsx` (e.g. in `C:\Temp\oo-test`).

(e) On Config, click *Choose size class file...*, pick it, then click *Check setup*; fix anything it lists in the same chat and paste again.

Step 4. Optional: what changed

Attach `size-class-master.xlsx` to show what the slide changed.

```
Attached is the previous size class list (first sheet; columns Name of machine and Size Class).
   Compare it with the final table from Step 3.

Rules: compare names ignoring capitals and spaces. Do not explain. Reply only in the format
   below.

Reply in exactly this format:
CLASS CHANGED
<Name of machine> | <previous Size Class> -> <new Size Class>
NEW (not in the previous list)
<Name of machine> | <Size Class>
DROPPED (in the previous list only)
<Name of machine> | <Size Class>
UNCHANGED: <number>
```