

CONSOLE API

For complete control over terminal formatting, Rich offers a `Console` class. Most applications will require a single `Console` instance, so you may want to create one at the module level or as an attribute of your top-level object. For example, you could add a file called “`console.py`” to your project:

```
from rich.console import Console
console = Console()
```

Then you can import the `console` from anywhere in your project like this:

```
from my_project.console import console
```

The `console` object handles the mechanics of generating ANSI escape sequences for color and style. It will auto-detect the capabilities of the terminal and convert colors if necessary.

2.1 Attributes

The `console` will auto-detect a number of properties required when rendering.

- `size` is the current dimensions of the terminal (which may change if you resize the window).
- `encoding` is the default encoding (typically “utf-8”).
- `is_terminal` is a boolean that indicates if the `Console` instance is writing to a terminal or not.
- `color_system` is a string containing the `Console` color system (see below).

2.2 Color systems

There are several “standards” for writing color to the terminal which are not all universally supported. Rich will auto-detect the appropriate color system, or you can set it manually by supplying a value for `color_system` to the `Console` constructor.

You can set `color_system` to one of the following values:

- `None` Disables color entirely.
- “`auto`” Will auto-detect the color system.
- “`standard`” Can display 8 colors, with normal and bright variations, for 16 colors in total.
- “`256`” Can display the 16 colors from “`standard`” plus a fixed palette of 240 colors.
- “`truecolor`” Can display 16.7 million colors, which is likely all the colors your monitor can display.
- “`windows`” Can display 8 colors in legacy Windows terminal. New Windows terminal can display “`truecolor`”.