accept(2) — Linux manual page

NAME I SYNOPSIS I DESCRIPTION I RETURN VALUE I ERRORS I VERSIONS I CONFORMING TO I NOTES I EXAMPLES I SEE ALSO I COLOPHON

Search online pages

ACCEPT(2)

Linux Programmer's Manual

ACCEPT(2)

NAME top

accept, accept4 - accept a connection on a socket

SYNOPSIS top

DESCRIPTION top

The accept() system call is used with connection-based socket types (SOCK_STREAM, SOCK_SEQPACKET). It extracts the first connection request on the queue of pending connections for the listening socket, sockfd, creates a new connected socket, and returns a new file descriptor referring to that socket. The newly created socket is not in the listening state. The original socket sockfd is unaffected by this call.

The argument sockfd is a socket that has been created with socket(2), bound to a local address with bind(2), and is listening for connections after a listen(2).

The argument addr is a pointer to a sockaddr structure. This structure is filled in with the address of the peer socket, as known to the communications layer. The exact format of the address returned addr is determined by the socket's address family (see socket(2) and the respective protocol man pages). When addr is NULL, nothing is filled in; in this case, addrlen is not used, and should also be NULL.

The addrlen argument is a value-result argument: the caller must initialize it to contain the size (in bytes) of the structure pointed to by addr; on return it will contain the actual size of the peer address.

The returned address is truncated if the buffer provided is too small; in this case, addrlen will return a value greater than was supplied to the call.

If no pending connections are present on the queue, and the socket is not marked as nonblocking, <code>accept()</code> blocks the caller until a connection is present. If the socket is marked nonblocking and no pending connections are present on the queue, <code>accept()</code> fails with the error <code>EAGAIN</code> or <code>EWOULDBLOCK</code>.

In order to be notified of incoming connections on a socket, you can use select(2), poll(2), or epoll(7). A readable event will be delivered when a new connection is attempted and you may then call accept() to get a socket for that connection. Alternatively, you can set the socket to deliver SIGIO when activity occurs on a socket; see socket(7) for details.

If flags is 0, then accept4() is the same as accept(). The following values can be bitwise ORed in flags to obtain different behavior:

SOCK NONBLOCK

Set the **O_NONBLOCK** file status flag on the open file description (see open(2)) referred to by the new file descriptor. Using this flag saves extra calls to fcntl(2) to achieve the same result.

SOCK CLOEXEC

Set the close-on-exec (**FD_CLOEXEC**) flag on the new file descriptor. See the description of the **O_CLOEXEC** flag in open(2) for reasons why this may be useful.

RETURN VALUE top

On success, these system calls return a file descriptor for the accepted socket (a nonnegative integer). On error, -1 is returned, erroo is set appropriately, and addrlen is left unchanged.

Error handling

Linux accept() (and accept4()) passes already-pending network errors on the new socket as an error code from accept(). This behavior differs from other BSD socket implementations. For reliable operation the application should detect the network errors defined for the protocol after accept() and treat them like EAGAIN by retrying. In the case of TCP/IP, these are ENETDOWN, EPROTO, ENOPROTOOPT, EHOSTDOWN, ENONET, EHOSTUNREACH, EOPNOTSUPP, and ENETUNREACH.

ERRORS top

EAGAIN or EWOULDBLOCK

The socket is marked nonblocking and no connections are present to be accepted. POSIX.1-2001 and POSIX.1-2008 allow either error to be returned for this case, and do not require these constants to have the same value, so a portable application should check for both possibilities.

EBADF sockfd is not an open file descriptor.

ECONNABORTED

A connection has been aborted.

- **EFAULT** The *addr* argument is not in a writable part of the user address space.
- **EINTR** The system call was interrupted by a signal that was caught before a valid connection arrived; see signal(7).
- **EINVAL** Socket is not listening for connections, or *addrlen* is invalid (e.g., is negative).
- EINVAL (accept4()) invalid value in flags.
- **EMFILE** The per-process limit on the number of open file descriptors has been reached.
- **ENFILE** The system-wide limit on the total number of open files has been reached.

ENOBUFS, ENOMEM

Not enough free memory. This often means that the memory allocation is limited by the socket buffer limits, not by the system memory.

ENOTSOCK

The file descriptor sockfd does not refer to a socket.

EOPNOTSUPP

The referenced socket is not of type SOCK STREAM.

EPROTO Protocol error.

In addition, Linux accept() may fail if:

EPERM Firewall rules forbid connection.

In addition, network errors for the new socket and as defined for the protocol may be returned. Various Linux kernels can return other errors such as ENOSR, ESOCKTNOSUPPORT, EPROTONOSUPPORT, ETIMEDOUT. The value ERESTARTSYS may be seen during a trace.

VERSIONS top

The accept4() system call is available starting with Linux 2.6.28; support in glibc is available starting with version 2.10.

CONFORMING TO top

accept(): POSIX.1-2001, POSIX.1-2008, SVr4, 4.4BSD (accept() first
appeared in 4.2BSD).

accept4() is a nonstandard Linux extension.

On Linux, the new socket returned by accept() does not inherit file status flags such as O NONBLOCK and O ASYNC from the listening

socket. This behavior differs from the canonical BSD sockets implementation. Portable programs should not rely on inheritance or noninheritance of file status flags and always explicitly set all required flags on the socket returned from accept().

NOTES top

POSIX.1-2001 does not require the inclusion of <sys/types.h>, and this header file is not required on Linux. However, some historical (BSD) implementations required this header file, and portable applications are probably wise to include it.

There may not always be a connection waiting after a **SIGIO** is delivered or select(2), poll(2), or epoll(7) return a readability event because the connection might have been removed by an asynchronous network error or another thread before **accept**() is called. If this happens, then the call will block waiting for the next connection to arrive. To ensure that **accept**() never blocks, the passed socket sockfd needs to have the **O_NONBLOCK** flag set (see socket(7)).

For certain protocols which require an explicit confirmation, such as DECnet, accept() can be thought of as merely dequeuing the next connection request and not implying confirmation. Confirmation can be implied by a normal read or write on the new file descriptor, and rejection can be implied by closing the new socket. Currently, only DECnet has these semantics on Linux.

The socklen t type

In the original BSD sockets implementation (and on other older systems) the third argument of accept() was declared as an int *. A POSIX.1g draft standard wanted to change it into a $size_t *C$; later POSIX standards and glibc 2.x have socklen t *.

EXAMPLES top

See bind(2).

SEE ALSO top

bind(2), connect(2), listen(2), select(2), socket(2), socket(7)

COLOPHON top

This page is part of release 5.08 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

Linux 2020-04-11 ACCEPT(2)

Pages that refer to this page: bind(2), connect(2), getpeername(2), getsockname(2), getsockopt(2), listen(2), _newselect(2), pselect(2), pselect(2), recv(2), recvfrom(2), recvmsg(2), select(2), select_tut(2), setsockopt(2), socket(2), socket(all(2), syscalls(2), endhostent(3),

fd_clr(3), FD_CLR(3), fd_isset(3), FD_ISSET(3), fd_set(3), FD_SET(3), fd_zero(3), FD_ZERO(3), freeaddrinfo(3), gai_strerror(3), getaddrinfo(3), gethostbyaddr(3), gethostbyaddr_r(3), gethostbyname2(3), gethostbyname2_r(3), gethostbyname(3), gethostbyname_r(3), gethostent(3), gethostent_r(3), getnameinfo(3), h_errno(3), herror(3), hstrerror(3), sethostent(3), capabilities(7), ddp(7), ip(7), sctp(7), signal(7), signal-safety(7), sock_diag(7), socket(7), tcp(7), unix(7)

Copyright and license for this manual page

HTML rendering created 2020-09-19 by Michael Kerrisk, author of *The Linux Programming Interface*, maintainer of the Linux *man-pages* project.

For details of in-depth **Linux/UNIX system programming training courses** that I teach, look here.

Hosting by jambit GmbH.



