


Feldfeste Operation Instruction



Feldfeste Games Studio

FF-OI-03: "Building setup"

Document History

Revision	Content	Editor	Time
01	Initial Document Creation	Arina	03.05.2026
02	Formal update	Arina	25.05.2026



Table of Contents

1. Building setup

Purpose of this document


Targets:

- Configure building blueprint defaults (tags, meshes, costs, components)
-


1 Building setup

Open the blueprint and enter Class Defaults

1) Set Individual tag.



For this tag, the data must be set in DT_Objects_info — class, icon, description, name
(/Content/CA_Code/Blueprints/Wiki/DT_Objects_info.uasset)




2) Meshes

All construction and destruction meshes need to be set. There must be at least 1 of each. There's no maximum — set as many as you want


Look at **BuildingConstructionMeshes** and **BuildingDestructionMeshes** in class defaults

Order matters! Documentation is written in the variable itself. Duplicating here:



Defines the visual state of the building based on its health percentage. The element at index 0 corresponds to 0% health and the element at the last index corresponds to 100% health



In splines, you also need to set up **PillarsMeshes**. For now, we're using the same meshes for Pillars in Construction and Destruction




For preview in the blueprints, you can set the mesh in BuildingMeshMaster



3) Construction cost

To set building cost, find **RequiredResources**. It's a map. Key is the resource, the value is the amount of that resource required for construction



For **splines**, look for the variables:

Resources Per Unit — this is the cost of a spline 'segment'. The segment length is in CostUnitDistance

Resources			
Resources Per Unit		2 Map elements	
Brick	200		
Stone	200		
Cost Unit Distance		300	
Non Edit			

4) Important components:

In **StabilityComponent**, set the building's max health. (Category: Attribute Default, Value: Init Max Value)

In **ResourceStorageComponent** — the building's storage settings.

The building limit settings shouldn't be set, because in the current implementation, the resource storage component for buildings is slightly different (Building Storage Component) and it acts as a proxy for the storage in Player State

5) Building-specific components



FF-OI-03: “Building setup” Rev(02)

There are components only for some buildings. They don't need to be added to the base blueprint, only to buildings that actually need them:

- **ResourceProduction** — component for buildings that produce something. It describes the conditions and possible production. (A production 'recipe' must also be in the production table.)
- **WorkersComponent** — component that handles the ability for someone to work in the building