

FGetPos

See Also

See **Fourier Transforms** on page III-270 for discussion. The inverse operation is **IFFT**.

Spectral Windowing on page III-275. For 2D windowing see **ImageWindow**. Also the **Hanning** window operation.

IFFT, DWT, CWT, STFT, HilbertTransform, WignerTransform, DSPPeriodogram, LombPeriodogram, Unwrap, MatrixOp

References

For more information about the use of window functions see:

Harris, F.J., "On the use of windows for harmonic analysis with the discrete Fourier Transform", *Proc, IEEE*, 66, 51-83, 1978.

Heinzel, G., Rüdiger, A., & Schilling, R. (2002). "Spectrum and spectral density estimation by the Discrete Fourier transform (DFT), including a comprehensive list of window functions and some new at-top windows", <http://hdl.handle.net/11858/00-001M-0000-0013-557A-5>.

FGetPos

FGetPos refNum

The FGetPos operation returns the file position for a file.

FGetPos is a faster alternative to FStatus if the only thing you are interested in is the file position.

The FGetPos operation was added in Igor Pro 7.00.

Parameters

refNum is a file reference number obtained from the **Open** operation.

Details

FGetPos supports very big files theoretically up to about 4.5E15 bytes in length.

FGetPos sets the following variables:

V_flag Nonzero (true) if *refNum* is valid.

V_filePos Current file position for the file in bytes from the start.

See Also

Open, FSetPos, FStatus

FIFO2Wave

FIFO2Wave [/R/S] FIFOName, channelName, waveName

The FIFO2Wave operation copies FIFO data from the specified channel of the named FIFO into the named wave. FIFOs are used for data acquisition.

Flags

/R=[startPoint,endPoint] Dumps the specified FIFO points into the wave.

/S=s Controls the wave's X scaling and number type:

s=0: Same as no /S.

s=1: Sets the wave's X scaling *x₀* value to the number of the first sample in the FIFO.

s=2: Changes the wave's number type to match the FIFO channel's type.

s=3: Combination of *s=1* and *s=2*.

Details

The FIFO must be in the valid state for FIFO2Wave to work. When you create a FIFO, using NewFIFO, it is initially invalid. It becomes valid when you issue the start command via the CtrlFIFO operation. It remains valid until you change a FIFO parameter using CtrlFIFO.