UNOFFICIAL USER GUIDE · DCS F-4E PHANTOM II

JESTER A/G+

AIR-TO-GROUND COMBAT ENHANCEMENT

JESTER

A/G+

VERSION 1.0 · OCTOBER 2026



A fan-made guide for a community mod. Not an official publication of Heatblur Simulations, Eagle Dynamics or the US Air Force. The emblem is original artwork.

START READ THIS FIRST

OVERVIEW

Jester A/G+ is an add-on for the Heatblur F-4E's Jester AI. It gives the back seat air-to-ground jobs that stock Jester does not do: keeping a list of targets, pointing the Pave Spike where you look and holding it on a target, slewing the Maverick seeker, setting the WRCS dials, and updating the INS from a TACAN station.

PURPOSE

Jester Pave Spike and Jester Maverick are stand-ins. Heatblur may eventually build these features properly in the module's own code, with full access to the pod and the seeker. Until then, A/G+ works with what the Jester modding interface exposes, and that is not everything (Section 7 explains what is missing for the Maverick).

The aim is to get the pod or the seeker close to the target and take workload off the pilot. The pilot finishes the attack. Jester will sometimes get a Maverick lock on his own; do not rely on it.

This guide assumes you know the F-4E's Pave Spike, WRCS and Maverick procedures. It covers what A/G+ adds and what it cannot do.

YOU WILL NEED

- The DCS F-4E with Jester's mod loader (the `mods\init` folder).
- The feed scripts in Section 1. Most of A/G+ depends on them.

Thank you to Heatblur for making outstanding DCS modules, and for making the F-4 Jester API available to the community.

SYMBOLS

WARNING

Can cost you the aircraft or a weapon.

CAUTION

Can break your install.

NOTE

Useful details.

CONTENTS

Section 1 Installing and the feeds 3
Section 2 The A/G Plus wheel 4
Section 3 The context button 5
Section 4 Finding targets: look there, search, Strike List 6
Section 5 Pave Spike with Jester 7
Section 6 WRCS, the one-shots and the INS update 9
Section 7 Jester Maverick 10
Section 8 Limits, troubleshooting and settings 13
Quick-reference card 14

TERMS

Term	Meaning
Strike List	Six target slots you fill and order. The pod and the Maverick both work from it.
Target List	Every unit a search has found. The Strike List is filled from it.
Context List	The short list on screen that a short press opens: the filled Strike List slots, then Search Area.
Look there	Jester points the pod at the ground spot you are looking at.
Hold	Jester keeps the pod on a vehicle or a ground spot.
Ground spot	A point on the terrain with no unit on it.
One-shot	A long press that sets a WRCS dial once, from the flight conditions at that moment.
Feed	A small script that runs inside DCS and writes what Jester cannot read for himself to a file.
J-Mav	Jester Maverick is working: Mavericks armed, DIRECT, TV, and Jester Maverick on.
ARR	The Air Refueling Release button on the stick. The BombBtnFeed lets Jester see it.
Dead reckoning	How Jester tracks where the Maverick seeker points without a readout (Section 7).

SECTION 1 INSTALLING AND THE FEEDS

INSTALLING

1. Close DCS and open your `Saved Games` folder.
2. Open `Saved Games\DCS_F4E\jester\mods` (create `mods` if it is missing). Drag the folders `agplus` and `init` from the download into it. Choose **Copy and Replace** when Windows asks. The folders merge and only A/G+ files are added.
3. Open `_EXTRA (DCS Scripts)` and drag the folder `Scripts` into `Saved Games\DCS` (`DCS.openbeta` for open beta). Choose **Copy and Replace**.
4. Export.lua: open the folder `Export.lua` inside `_EXTRA (DCS Scripts)`. If you have no `Saved Games\DCS\Scripts\Export.lua`, drag and drop that file into `Saved Games\DCS\Scripts`. If you already have one, leave it and add this one line at its end, on a line of its own:
   `pcall(function() local l=require("lfs"); dofile(l.writedir().. [[Scripts\AGPlus\AGPlusLoad.lua]]) end)`
   If you also use Jester Survivability, its line goes on a separate line after this one.
5. Open `DCS_F4E\jester\mods\agplus\Config.lua` and set the three paths at the top: `SAVED_GAMES`, `DCS_SAVED_FOLDER` and `DCS_INSTALL`.
6. Restart DCS. Feeds and hooks load only when DCS starts.

To switch A/G+ off, delete `mods\init\agplus`. A/G+ never replaces a stock Jester file.

THE FEEDS

Jester's own Lua cannot see the stores on the pylons, the pilot's buttons, other units or the terrain. Small scripts that run inside DCS read these and leave them in text files for Jester.

File	Without it
AGPlusFeed.lua	No Weapon readout, no Maverick loadout, no one-shots.
BombBtnFeed.lua	Jester cannot see your pickle or ARR (Air Refueling Release) button: no Maverick hand-over or After Launch, no pod freeze on release.
PaveProbeFeed.lua + PaveProbeHook.lua	No look there, no searches, no ground spots, no laser masking.
PaveDebugHook.lua + MessageOverlay.dlg	No on-screen messages, so no Target Lists either.


NOTE

A/G+ needs no MissionScripting.lua edit. Its feeds run in Export and its hooks in the GUI, so DCS's io stays sanitized.

CAUTION

Drag and drop the supplied Export.lua only if you have none. Tacview, SRS and DCS-BIOS use Export.lua too, so never copy a new one over yours; add the one line at the end and leave the rest alone.

`INSTALL.md` has a check that the feeds are running, and troubleshooting.



Jester's own Lua cannot reach the stores, the pilot's buttons, other units or the terrain. The feeds read them and leave files for Jester.

FIG. 1-1. HOW JESTER LEARNS WHAT HE CANNOT SEE.

WARNING

Object export. Searches and holds need DCS object export, which lists the units around you. A multiplayer server can switch object export off. On such a server the searches find nothing, the Target Lists stay empty, and Jester cannot hold any target with the pod, a ground spot included. The drag coefficient one-shot needs a hold, so it does not work either. Look there, the OFFSET release range and the INS update still work.

SECTION 2 THE A/G PLUS WHEEL

A/G+ adds one item, **A/G Plus**, to the Air To Ground page of the Jester wheel. Everything else sits inside it, except INS Update, which is on the Navigation page.

Air To Ground > A/G Plus

Strike List

Slots 1 to 6: Go To, Choose From List, Use Current Target, Move Up / Down, Clear Slot, Delete Unit

Full Target List: Refresh Target Data, Purge Targets, each category with its units

Manage: Fill From Target List, Add Current Target, Clear All, Auto Fill, Auto Advance

Maverick

Jester Maverick On / Off, FOV, After Launch, Seeker (After Slew, Lock Now, Cage Seeker)

Pave Spike

Search Area, Laser (Auto, On, Off), Mode (12 Vis, WRCS, 9 Vis)

WRCS Integration

Target Insert, Map Marks, Reset Target Data, Mag Variation

Weapon

GP Bombs, Precision / LGB, Cluster Munitions

Navigation > INS Update

Overfly TACAN, Fix By Bearing

FIG. 2-1. THE MENUS. HIGHLIGHTED: THE A/G PLUS RING.

THE CENTER READOUT

The middle of the A/G Plus ring shows three lines.

Line	Shows
Weapon	The bombs and Mavericks on the armed stations, for example *Mk-82 LD + AGM-65A*. MIXED when more than one bomb type is armed.
Mode	The Delivery Mode knob: Direct, TGT Find or Offset. J-Mav while Jester Maverick is working.
Target	The target the pod holds, or the one Jester is waiting to reacquire.

WEAPON MENU

The weapon follows the armed stations by itself. The Weapon menu is for the OFFSET one-shot with no bomb armed yet: pick the bomb you will drop. A weapon picked by hand stays until the armed stations change.




FIG. 2-2. THE A/G PLUS RING.

SECTION 3 THE CONTEXT BUTTON

Most of A/G+ runs from the context button: short, long and double presses. A/G+ takes the press only in the cases below. In every other case the press goes to stock Jester unchanged, so the radar and every other context action work as before.




FIG. 3-1. WHO ANSWERS A PRESS.

THE ONE-SHOTS

A long press can set a WRCS dial once, from the flight conditions at that moment. Set it on the run in, at the speed and height you will release at. Jester does not keep the dial updated afterwards.

Delivery Mode	Long press sets
TGT FIND, pod holding a target	Drag Coefficient for the armed laser-guided bomb, from altitude, speed and dive angle. On a moving vehicle it also sets a lead point (Section 5).
OFFSET	Release Range and its x10/x100 switch for the armed bomb, from true airspeed and height above the target.

A message confirms the value. Jester answers "unable" and the message says why when no bomb is armed, when more than one bomb type is armed, when the weapon is not one the tables cover, when the bomb has no table for that dial, or, for the release range, when Jester has no airspeed or altitude reading.

THE CONTEXT LIST ON SCREEN

The Pave Spike and the Maverick both open a Context List from a short press. It holds the filled Strike List slots (the Pave Spike's can hold every listed unit instead, see Context List under Manage in Section 4), then Search Area; with a lost target waiting that is in no slot, Reacquire comes first. The list opens even when the Strike List is empty. Each press steps the cursor: short goes to the next entry, double to the previous one. After a short pause following the last press, Jester goes to the entry under the cursor. The last entry, Search Area, starts a search.




FIG. 3-2. THE CONTEXT LIST.

Mark	Means
=>	The cursor. Jester goes here after the pause.
*	The current target.
>>>	Right of the nose; more arrows, farther off. < is left.
>^<	Dead ahead.
!!!	Outside the limits of the pod or seeker.
(words)	Where the target lies, in plain words.

SECTION 4 FINDING TARGETS

LOOK THERE

With the Pave Spike active and nothing held, look at a spot on the ground and long press. Jester takes the pod into track and slews it to where you are looking. The pod still takes time to slew. In TGT FIND, Jester also sets the Target Alt/Range dial to the terrain height under the pod.

Jester answers "unable" when you are looking into the cockpit, or above the aircraft's datum line, where the pod cannot look. A spot in the pod's blind zone behind the tail is remembered, and Jester slews to it once it is clear.

SEARCH

Choose **Pave Spike, Search Area**, or Search Area at the end of the Context List. From the Context List, step to Search Area and pause, with no trip through the wheel. The pod must be in track; a hold is let go first, and a caged pod is refused (long press to look there first). Jester sweeps the pod around the spot it is on and lists every hostile ground unit he could plausibly pick out: inside the area, in line of sight from the aircraft, and close enough to recognize. Small units need a closer look than large ones. A count shows on screen while he searches. The pod goes back to where it started, zoom included. Leaving TGT FIND ends any hold or search.

The Maverick has its own search (Section 7).

THE TARGET LIST

Every unit found joins the Target List, sorted into categories (Anti Air, Armor, Vehicles, Infantry, Structures). It is under **Strike List, Full Target List**. Each unit has **Select** (the pod goes to it) and **Delete Unit**. **Refresh Target Data** redraws the list; **Purge Targets** forgets every target, clears the Strike List and switches the laser off.

THE STRIKE LIST

Six slots, in the order you attack. The Maverick's Context List always steps through it, and so does the pod's unless you set Context List to Full List (below).

Item	Does
Go To	The pod goes to the slot.
Choose From List	Fill the slot from the Target List.
Use Current Target	Put the target the pod holds into the slot.
Move Up / Down	Reorder.
Clear Slot	Empty the slot. Auto Fill leaves that unit alone.
Delete Unit	Remove the unit from both lists.

Manage holds Fill From Target List, Add Current Target, Clear All and three switches:

- **Auto Fill** (on): units that join the Target List, from a search, a designation or a spotted unit, go into empty slots.
- **Auto Advance** (on): after a weapon is released on the held Strike List target and the pass is over, with the laser off, the pod moves to the next filled slot. After the last filled slot it goes back to the first one; "Strike List Complete" shows only when no other slot is filled.
- **Context List** (Strike List): what the pod's Context List steps through. **Strike List** is the filled slots. **Full List** is every unit in the Target List, and the pod goes to the unit even when it is in no slot. Search Area and Reacquire stay in the list either way. The Maverick's list is not affected.

DESTROYED TARGETS

A listed unit that has been destroyed leaves the Target List and the Strike List after a few seconds, whoever destroyed it, and Auto Fill refills the freed slot. Only the current target (the one held or last held) is announced: **Target Destroyed** and its name. If it is the one the pod is holding, the hold ends and the laser goes off, and with Auto Advance on the pod goes to the next filled slot (looping after the last) once the laser is off. The wheel jumps back to the Strike List page so the lists redraw. Statics, and units farther than about 24 NM from you, are never removed. While the pod is idle, Jester checks for kills every few seconds.




FIG. 4-1. A SEARCH IN PROGRESS.

SECTION 5 PAVE SPIKE WITH JESTER

These presses apply while the Pave Spike is the active system, normally with the Delivery Mode in TGT FIND. In OFFSET a long press sets the release range instead (Section 6), unless the pod is active and holding nothing. Questions are read from the top; the first YES decides.




FIG. 5-1. SHORT PRESS.




FIG. 5-2. LONG PRESS.




FIG. 5-3. DOUBLE PRESS.

HOLDING A TARGET

A short press in track holds the vehicle nearest the crosshair, or the ground spot under it when there is none. Jester then flies the hand control to keep the pod on it, moving vehicles included.

Holding a target adds it, and the other vehicles in the picture, to the Target Lists. The target line in the center readout names what is held.

THE LASER

Pave Spike, Laser has three settings.

Setting	Jester
Auto	Switches the laser on as you close on the held target, off while terrain hides it, and off after the pass.
On	Laser on now. Jester no longer switches it.
Off	Laser off now. Jester no longer switches it.

The laser code is set with the stock Jester item.

RELEASING

The pod cannot be moved while the weapon release button is held. Jester sees the button through BombBtnFeed.lua and stops steering until you let go, then picks the target up again. Keep the button held until the bomb leaves, then let go.

MOVING TARGETS

When the held target is a moving vehicle, the long press that sets the drag coefficient also sets a lead point. The pod moves ahead of the vehicle to where it will be when the bomb picks up the laser, and stays there through the release. When you let go of the release button the pod goes back to the vehicle, and the laser guides the bomb onto it. If you do not release in time, the pod goes back by itself.

NOTE

Hold the target for a few seconds first, so Jester can measure how it moves. Set the drag coefficient on the final run-in, at the height and speed you will release at. The lead point is worked out from that moment.

LOSING A TARGET

When the pod drops a held target, Jester remembers it. With the pod in memory he reacquires it by himself once it is back inside the pod's limits; the center readout shows the target as waiting. A short press meanwhile opens the Context List. A Strike List unit you pick becomes the one he reacquires; **Reacquire** goes to the lost target at once. A long press forgets the target. A double press forgets it and cages the pod.

MODE

Pave Spike, Mode sets the acquisition mode: 12 Vis, WRCS or 9 Vis.

LIMITS

- The pod cannot look above the datum line or into its blind zone behind the tail. Jester waits for a target there to come clear.
- Jester takes the pod into track with the hand-control trigger; if the WSO scope is not on TV he switches it first.
- The regular Pave Spike is harder to steer across the nose than the Smart-Track and Fast-Track pods. Expect slower slews there.



FIG. 5-4. A HOLD ON A VEHICLE.

Section 6 WRCS, ONE-SHOTS AND INS UPDATE

TARGET INSERT

Pick a map marker under **WRCS Integration, Map Marks**, then choose **Target Insert**. Jester freezes the cursor, dials the north/south and east/west offsets and the target altitude into the WRCS, presses Insert, and slaves the Pave Spike to the point. A marker beyond 16.4 NM, the WRCS offset limit, is refused.

Item	Does
Map Marks: Refresh Markers	Reads the map markers again.
Nearest Markers / Own Markers	Every marker near you, or only yours.
Reset Target Data	Jester presses the WRCS Reset.
Mag Variation	Auto (by map), fine and coarse adjust, presets.

A/G+ compensates for magnetic variation on each map. Set it by hand under Mag Variation if it is off.

The center readout of the WRCS menus shows the weapon, the selected marker with its altitude and distance, and the variation.

RELEASE RANGE (OFFSET)

With the Delivery Mode in OFFSET, a long press sets the Release Range dial and its x10/x100 switch for the armed bomb. Jester works it out from your true airspeed and your height above the target: the selected marker's altitude, or the ground under you when no marker is selected. If the pod is active but holding nothing, the long press stays a Pave Spike press, and a running search ends first. The table assumes a level release.

DRAG COEFFICIENT (TGT FIND)

With the pod holding a target in TGT FIND, a long press sets the Drag Coefficient dial for the armed laser-guided bomb from your altitude, speed and dive angle (Section 5).

WHICH BOMBS

The drag coefficient covers the GBU-10, GBU-12 and GBU-24. The release range covers the Mk-82 (LD, Snakeye and AIR), Mk-83, Mk-84, the three GBUs and the CBU-87. The Weapon menu lists the same bombs.

NOTE

Both one-shots set the dial once. Climb, descend or change speed afterwards and the value is no longer valid: long press again.

INS UPDATE FROM TACAN

Navigation, INS Update has two ways to correct the INS from a TACAN station. Jester picks the station from the map's beacon list (the airfield beacons built into the map), takes NAV CMD, tunes his own TACAN, runs the stock nav fix, then puts his TACAN back and hands NAV CMD back.

Item	How
Overfly TACAN	Fly over the station. Jester uses the nearest station, keys in its position early and flips FIX as you cross it. Passing well to one side of the station gives no fix. If the crossing is missed, he works the fix out from the range after the station.
Fix By Bearing	Jester takes the bearing and range to a nearby station and works out where you are. It takes him a little while, as it would take a WSO with a chart.

The front seat's bearing/distance selector must be on a TACAN position. While it is not, both items show ***UNABLE***.

Range

A TACAN bearing is good to about a degree. At 100 NM that is about 1.7 NM sideways, which can be worse than the INS error you are trying to fix. Fix By Bearing therefore uses only nearby stations; for a far station, overfly it.

NOTE

Carrier TACANs and beacons placed in the mission are not in the map's list, so Jester does not use them.

SECTION 7 JESTER MAVERICK

WHAT JESTER DOES

Jester gets the Maverick seeker onto a Strike List target, or searches with it, and hands it to you. You confirm the target, lock and fire.

- Slews the seeker to the target you pick from the list.
- Searches the ground you are looking at and adds what he finds to the Strike List.
- Keeps track of each missile's cap and field of view.
- Moves to the next target after a launch.

Jester Maverick works with the A, B, D and G. It needs the Mavericks armed, Delivery Mode in DIRECT and Weapon Select on TV. It turns itself on each time those three become true while it is off; **Maverick, Jester Maverick** turns it off.

WARNING

Wait for the Mavericks to finish warming up, with the station ARM lights on, before you open the Maverick Context List or long press. A slew starts by taking the cap off, and taking the cap off a cold missile damages it.

WHAT JESTER CANNOT DO, AND WHY

The modding interface does not expose the Maverick seeker. Jester cannot read where it points, whether it is locked, which field of view it is in, or whether the cap is on. Everything Jester does with the seeker is worked out from what he and you did with the controls.

So Jester does not lock or fire on purpose. He gets the seeker close and you finish. With **After Slew: Lock**, Jester lets go of the hand-control trigger when his estimate sits on the target, and sometimes the seeker locks. Heatblur, working in the module's own code, could do this properly.




FIG. 7-1. DEAD RECKONING THE SEEKER.

DEAD RECKONING

A caged seeker points at the boresight, so after a cage Jester knows where it is. From there he slews with the hand control, and adds up how far each stick input moves the seeker. Every slew starts from a cage, unless the seeker is already caged. The seeker's slew rates, gimbal limits and picture sizes were measured in the sim for each variant, so the estimate holds well over one slew.

The estimate is lost when you slew the seeker yourself, after a lock attempt, and after a frame stutter long enough to throw the estimate off. Jester then cages again before the next slew. That is why the seeker returns to the boresight before most slews.

These presses apply in DIRECT with Weapon Select on TV and Jester Maverick on. Questions are read from the top; the first YES decides.




FIG. 7-2. SHORT OR DOUBLE PRESS.




FIG. 7-3. LONG PRESS.

SLEWING TO A TARGET

Open the Context List, step to the target and pause. The seeker cages while you choose; then Jester slews. A message names the slot and where it lies. A target outside the seeker's limits gets "unable" and the reason. A press during a slew ends it and opens the Context List again.

Seeker in the Maverick menu sets what happens after the slew:

Item	Does
After Slew: Lock	Jester lets go of the hand-control trigger when his estimate is on the target: a lock attempt.
After Slew: Hold	Jester keeps the seeker on his estimate, hand-control trigger held, until you press, take over or choose Lock Now.
Lock Now	Jester lets go of the hand-control trigger now.
Cage Seeker	Jester cages the seeker.

SEARCH

Look at a spot on the ground and long press. Jester slews the seeker there and flies a spiral around that spot, held over the same ground as you fly on. Every hostile unit that passes through the picture, close enough to see and in line of sight, joins the Target List and, with Auto Fill, the Strike List. Search Area at the end of the Context List searches from the boresight instead.

The search ends by itself when it is complete or reaches the seeker's limit, and the seeker cages. Jester answers "unable" when the spot is outside the seeker's limits or there is no ground there. A D or G searches in narrow; Jester puts your field of view back before the cage.

CAP AND FIELD OF VIEW

Jester tracks the cap and the field of view of each missile on its own. A fresh missile has its cap on and, on the D and G, starts in wide. Jester takes the cap off before the first slew: on the A and B by holding the hand-control trigger, on the D and G with a normal press. If Jester has the field of view wrong, set **Maverick, FOV** to what the display shows.

Jester cannot read the field of view, so it can drift out of step with the seeker, for example around the lock bug or a cage. In most cases you can bring them back together yourself: tap ARR, then double tap the trigger.

TAKING THE SEEKER

Jester watches your controls and lets go when you take over. What he assumes about the seeker afterwards:

You	Jester
Slew the seeker (ARR held, hand control off center)	Lets go at once. The seeker position is now unknown.
Tap ARR briefly without slewing	Lets go and counts the seeker as caged. Use it when Jester's idea of the seeker is stuck.
Your trigger, full action, A or B	Lets go and counts the seeker as caged.
Your trigger, full action, D or G	A field-of-view change while the seeker is caged, ARR is held or the half action is held; otherwise a cage.
Your first trigger press on a capped missile	Cap off only: no cage, no field-of-view change.

The rules for your trigger apply with Master Arm on.

AFTER LAUNCH

After Launch: Next (the default) moves to the next Strike List target after a shot. **After Launch: Stop** leaves the target where it is.

Jester counts a launch when your pickle is held long enough for the missile to leave and the missile count drops. He reads the pickle from BombBtnFeed and the missile count from AGPlusFeed. It works with single and triple rails. The next missile on the station is fresh, with its cap on. When its cap comes off, by Jester's press or yours, Jester's Maverick target moves to the next Strike List slot.



FIG. 7-4. AFTER LAUNCH: NEXT.

LIMITS

- Jester does not lock or fire on purpose. Do not rely on a lock from After Slew: Lock.
- The seeker position is an estimate. Over a long slew it can drift by a fraction of the picture; finish the last bit yourself.
- Jester cages before most slews, so each slew starts with a short wait.
- A stutter, your own slew or a lock attempt makes the position unknown until the next cage.
- Jester cannot see a lock, the cap or the field of view on the display. If he has the field of view wrong, correct it in the menu.
- The Maverick search needs the feeds and object export, the same as the pod's.

NOTE

Jester Maverick is a stand-in until Heatblur exposes the seeker. The best results come from letting Jester do the coarse slew and doing the fine work yourself.




FIG. 7-5. THE MAVERICK MENU.

Section 8 LIMITS, TROUBLESHOOTING AND SETTINGS

LIMITS

- Jester Pave Spike and Jester Maverick are stand-ins. They get you close and take workload off; they do not replace the pilot.
- Searches and holds need object export (Section 1). Without it the Target Lists stay empty and the pod cannot hold a target.
- On a multiplayer server you have joined, static objects such as buildings are read from the mission file you loaded: their starting positions only. Statics that a mission script spawned are missed, and destroyed ones stay listed. Units come from object export.
- Jester cannot read the Maverick seeker. Its position is dead reckoned and its field of view is tracked, not read, so the field of view can drift out of step. In most cases tap ARR, then double tap the trigger (Section 7).
- Jester works the pod and seeker with the same hand control and trigger you have, at the same speeds.
- Jester's hands are busy while he works. Other wheel jobs queue behind it.

IF NOTHING HAPPENS

- No A/G Plus item: check `mods\init\agplus` exists.
- Weapon shows none with bombs armed: AGPlusFeed is not running, or `DCS_SAVED_FOLDER` is wrong.
- No messages and no Target List: the message hook is missing, or DCS was not restarted.
- Look there does nothing: PaveProbeFeed or PaveProbeHook is missing.
- Searches and holds do nothing: the same, or the server has object export off.
- Jester does not let go when you press ARR: BombBtnFeed is missing or old.

For a bug report, set `LOG_TO_FILE = true` and send `agplus\agplus.log`.

SETTINGS

All settings are in `agplus\Config.lua`, each with a comment. The ones you may want:

Setting	Effect
SAVED_GAMES, DCS_SAVED_FOLDER, DCS_INSTALL	Your paths (Section 1).
LOG_TO_FILE	Writes agplus.log.
MAV_AUTO_ON	false: Jester Maverick does not turn itself on.
MAV_PICK_DWELL_S	The pause before Jester goes to the list cursor.
MAV_LIST_NOTES	false: arrows only, no words, in the Target List.
MAV_SEARCH_LOOK	false: the long press searches from the boresight.
PAVE_AUTO_REACQUIRE	false: Jester does not reacquire a lost target by himself.
PAVE_LEAD	false: no lead point on moving targets.
STRIKE_AUTO_FILL, STRIKE_AUTO_ADVANCE	The starting state of the two Strike List switches.
CONTEXT_LIST_SOURCE	'strike' or 'full': the starting state of the Context List switch.
PAVE_REMOVE_DEAD	false: destroyed targets stay in the lists.
PAVE_DEAD_REDRAW	false: the wheel does not jump back to the Strike List page after a removal.

CARD QUICK REFERENCE

PAVE SPIKE (TGT FIND)

Press	Does
Short	Pod caged, holding or waiting: open the Context List (Search Area is always in it). In track, nothing held: hold what is under the crosshair.
Long	Look there. Holding a target: set the drag coefficient (and lead point).
Double	Let go of the hold, search or slew. Idle: cage the pod.

MAVERICK (DIRECT + TV)

Press	Does
Short / double	Open the Context List, step next / previous. Pause to slew.
Long	Search where you look. Context List open: close it.
Double, searching	Cancel the search.

Print at 50% for a kneeboard card.

OFFSET

Press	Does
Long	Set the release range for the armed bomb.

TAKING OVER THE MAVERICK

You	Jester
ARR + slew	Lets go; position unknown.
ARR tap	Lets go; seeker counted caged.
Your trigger, A/B	Lets go; seeker counted caged.
Your trigger, D/G	FOV change when caged, ARR or half action held; else caged.

WARNING

Mavericks: wait for the ARM lights before the first slew.

NOTE

LShift+R restarts the mission and reloads Jester's Lua. Feeds and hooks need a DCS restart.