

config/settings.py

```
'allauth.account.auth_backends.AuthenticationBackend',
]

# LOGIN and LOGOUT Redirection
LOGIN_REDIRECT_URL = '/'
ACCOUNT_LOGOUT_REDIRECT_URL = '/accounts/login/'
# ACCOUNT_LOGOUT_ON_GET = True
```

Change account authentication method to email

Lastly, add the code below. In this example, we'll use the email authentication approach, which has been recently more common than the username authentication approach. But for email verification, set it as `"none"` for now. We'll cover email verification settings later in this chapter.

config/settings.py

```
ACCOUNT_LOGOUT_REDIRECT_URL = '/accounts/login/'
# ACCOUNT_LOGOUT_ON_GET = True

ACCOUNT_AUTHENTICATION_METHOD = "email"
ACCOUNT_EMAIL_REQUIRED = True
ACCOUNT_EMAIL_VERIFICATION = "none"

ACCOUNT_USERNAME_REQUIRED = False
ACCOUNT_UNIQUE_USERNAME = False

#Add the following when you are using custom user model
#ACCOUNT_USER_MODEL_USERNAME_FIELD = None
```

3. Edit urls.py

As you need to connect between the main *urls.py* and the *urls.py* under *allauth* directory, add a new path in the main *urls.py* shown below.

config/urls.py

```
urlpatterns = [
    :
    path('accounts/', include('allauth.urls')),
]
```

The *urls.py* under the *allauth* directory is linked with another *urls.py* file under the *account* directory.