

Command Line - RESPONSE

```
:  
Successfully installed Django-4.1.7 asgiref-3.6.0  
backports.zoneinfo-0.2.1 certifi-2022.12.7 cffi-1.15.1 charset-  
normalizer-3.1.0 crispy-bootstrap5-0.7 cryptography-40.0.2  
defusedxml-0.7.1 django-allauth-0.54.0 django-crispy-forms-2.0  
django-enviro-0.10.0 gunicorn-20.1.0 idna-3.4 oauthlib-3.2.2  
psycopg2-binary-2.9.6 pycparser-2.21 pyjwt-2.6.0 python3-openid-  
3.2.0 requests-2.28.2 requests-oauthlib-1.3.1 sqlparse-0.4.4  
urllib3-1.26.15
```

Run the Django setup commands

No database is migrated at this stage, and no superuser is created.
Run the as-usual commands on the server.

Command Line - INPUT

```
ubuntu@ip-xx:~/project_d$ | python manage.py makemigrations  
ubuntu@ip-xx:~/project_d$ | python manage.py migrate  
ubuntu@ip-xx:~/project_d$ | python manage.py createsuperuser
```

Note: Database Owner

When you run the migrate command, you may encounter an error like the one shown below.

Command Line - RESPONSE

```
...django.db.migrations.exceptions.MigrationSchemaMissing: Unable  
to create the django_migrations table (permission denied for sche  
public  
LINE 1: CREATE TABLE "django_migrations" ("id" bigint NOT NULL  
PRIMA...
```

This may be because of the database owner setting for PostgreSQL. This setting was not required in the older version of PostgreSQL, but it is required in the recent versions. To set it up, run the command below after entering the PostgreSQL prompt.

Command Line - INPUT

```
[user@localhost] | ALTER DATABASE project_d OWNER TO  
project_d_user;
```

When it is successful, the command line returns the message below.