

configuration. As the configuration files saved in this directory are always read by Nginx, there is limited flexibility to switch configurations.

3. **sites-available directory:** this is another directory where you can save your custom configuration files; however, Nginx does not read the files directly. To enable the configuration, you need to create a symbolic link of the file in the *sites-enabled* directory. By following this rule, you can easily switch configuration files by controlling symbolic links.
4. **sites-enabled directory:** the location where you can put the symbolic link of the configuration file that was created in the *sites-available* directory.

To create a new configuration file, run the command below.

Command Line - INPUT

```
ubuntu@ip-xx:~$ | sudo vim /etc/nginx/sites-available/project_d
```

Edit the file like in the example below.

/etc/nginx/sites-available/project_d

```
server {
    listen 80;
    server_name xx.xx.xx.xx;

    location = /favicon.ico { access_log off; log_not_found off;}
    location /static{
        alias /usr/share/nginx/html/static;
    }
    location / {
        include proxy_params;
        proxy_pass http://unix:/home/ubuntu/project_d/project_d.sock;
    }
}
```

There are three key parts that you need to type carefully.

1. **server name:** the **static IP address** attached to the Ubuntu instance
2. **location /static:** the address should be aligned with `STATIC_ROOT`
3. **proxy_pass:** the path of the `sock` file defined in the Unicorn service and socket unit files in the previous section