

during the game reset when we start a new game. Here's the `__init__()` method for *settings.py*:

```
settings.py    def __init__(self):
                """Initialize the game's static settings."""
                # Screen settings
                self.screen_width = 1200
                self.screen_height = 800
                self.bg_color = (230, 230, 230)

                # Ship settings
                self.ship_limit = 3

                # Bullet settings
                self.bullet_width = 3
                self.bullet_height = 15
                self.bullet_color = 60, 60, 60
                self.bullets_allowed = 3

                # Alien settings
                self.fleet_drop_speed = 10

                # How quickly the game speeds up
                ❶ self.speedup_scale = 1.1

                ❷ self.initialize_dynamic_settings()
```

We continue to initialize settings that stay constant in the `__init__()` method. We add a `speedup_scale` setting ❶ to control how quickly the game speeds up: a value of 2 will double the game speed every time the player reaches a new level; a value of 1 will keep the speed constant. A value like 1.1 should increase the speed enough to make the game challenging but not impossible. Finally, we call the `initialize_dynamic_settings()` method to initialize the values for attributes that need to change throughout the game ❷.

Here's the code for `initialize_dynamic_settings()`:

```
settings.py    def initialize_dynamic_settings(self):
                """Initialize settings that change throughout the game."""
                self.ship_speed = 1.5
                self.bullet_speed = 2.5
                self.alien_speed = 1.0

                # fleet_direction of 1 represents right; -1 represents left.
                self.fleet_direction = 1
```

This method sets the initial values for the ship, bullet, and alien speeds. We'll increase these speeds as the player progresses in the game and reset them each time the player starts a new game. We include `fleet_direction` in this method so the aliens always move right at the beginning of a new game. We don't need to increase the value of `fleet_drop_speed`,