

- Calls the `update()` method ❹ to allow the scene to do any per-frame actions. The `Scene` base class implements an `update()` method that just contains a `pass` statement, but a scene can override this method with any code it wants to execute.
- Calls the `draw()` method ❺ to allow the scene to draw anything it needs to draw in the window.

At the bottom of the loop (identical to the standard main loop without a scene manager), the method updates the window ❻ and waits for an appropriate amount of time.

Main Methods

The remaining methods of the `SceneMgr` class implement the navigation and communication between scenes:

`_goToScene()` Called to transfer to a different scene

`_request_respond()` Called to query data in another scene

`_send_receive()` Called to send information from one scene to another

`_sendAll_receive()` Called to send information from one scene to all other scenes

The code of any scenes that you write should not call these methods directly, and they should not be overwritten. The underscore in front of their names implies that these are private (internal) methods. While they are not called directly within the scene manager itself, they are called by the `Scene` base class.

To explain how these methods work, I'll start by giving an overview of the steps involved when a scene wants to navigate to another scene. To make a transition to a target scene, the current scene calls:

```
self.goToScene(SOME_SCENE_KEY)
```

When a scene makes this call, the call goes to the `goToScene()` method in the inherited `Scene` base class. The code of the inherited method consists of a