

```
self.quitButton.disable()
pygame.mouse.set_visible(False)
```

Listing 16-4: The `enter()`, `getHiAndLowScores()`, and `reset()` methods of the `ScenePlay` class

When navigating to the Play scene, the scene manager calls `enter()` ❶, which in turn calls the `getHiAndLowScores()` method ❷. That method issues a request to the High Scores scene ❸ to retrieve the highest and lowest scores from the high scores table, so we can draw the highest score from that table in the bar at the bottom of the window. At the end of each game, it compares the game's score to the lowest top 10 score to see if this game ranks in the top 10.

When the user clicks the New Game button, the `reset()` method ❹ is called to reinitialize everything that needs to be reset before starting a new round of the game. The `reset()` method tells the Baddie manager and the Goodie manager to reinitialize themselves by calling their own `reset()` methods ❺, disables the buttons at the bottom of the screen so they cannot be pressed during game play ❻, and hides the pointer cursor. During play, the user moves the mouse to control the Player icon in the window.

The code in [Listing 16-5](#) deals with user input.

```
❶ def handleInputs(self, eventsList, keyPressedList):
    ❷ if self.playingState == STATE_PLAYING:
        return # ignore button events while playing

    for event in eventsList:
        ❸ if self.startButton.handleEvent(event):
            self.reset()
            self.playingState = STATE_PLAYING

        ❹ if self.highScoresButton.handleEvent(event):
            self.goToScene(SCENE_HIGH_SCORES)

        ❺ if self.soundCheckBox.handleEvent(event):
            self.backgroundMusic = self.soundCheckBox.getValue()

        ❻ if self.quitButton.handleEvent(event):
            self.quit()
```
