WARNING You might run into the following error: “Your requested instance type (`m6id.large`) is not supported in your requested Availability Zone.” Not all regions/availability zones support `m6id.large` instance types. Select a different subnet and try again.

```
$ lsblk
NAME          MAJ:MIN RM   SIZE RO TYPE MOUNTPOINT
nvme1n1       259:0    0 109.9G  0 disk    ①
nvme0n1       259:1    0     8G  0 disk    ②
├─nvme0n1p1   259:2    0     8G  0 part /
└─nvme0n1p128 259:3    0     1M  0 part
```

① The instance store device

② The EBS root volume device

To see the mounted volumes, use this command:

```
$ df -h
Filesystem      Size  Used Avail Use% Mounted on
devtmpfs        3.9G     0  3.9G   0% /dev
tmpfs           3.9G     0  3.9G   0% /dev/shm
tmpfs           3.9G  348K  3.9G   1% /run
tmpfs           3.9G     0  3.9G   0% /sys/fs/cgroup
/dev/nvme0n1p1  8.0G  1.5G  6.6G  19% /      ①
```

① The EBS root volume contains the OS.

Your instance store volume is not yet usable. You have to format the device and mount it as follows:

```
$ sudo mkfs -t xfs /dev/nvme1n1     ①
$ sudo mkdir /data                  ②
$ sudo mount /dev/nvme1n1 /data     ③
```

① Formats by creating an XFS filesystem

② Creates a folder on which to mount the device

③ Mounts the device