For the `todo-user` table, we recommend you use the `uid` as the primary key because the attribute is unique. Also, the only command that queries data is `user`, which fetches a user by its `uid`. When using a single attribute as primary key, DynamoDB calls this the *partition key* of the table.

You can create a table by using the Management Console, CloudFormation, SDKs, or the CLI. Within this chapter, we use the AWS CLI. The `aws dynamodb create-table` command has the following four mandatory options:

- `table-name`—Name of the table (can't be changed).
- `attribute-definitions`—Name and type of attributes used as the primary key. Multiple definitions can be given using the syntax `AttributeName=attr1`, `AttributeType=S`, separated by a space character. Valid types are `S` (string), `N` (number), and `B` (binary).
- `key-schema`—Name of attributes that are part of the primary key (can't be changed). Contains a single entry using the syntax `AttributeName=attr1, KeyType=HASH` for a partition key, or two entries separated by spaces for a partition key and sort key. Valid types are `HASH` and `RANGE`.
- `provisioned-throughput`—Performance settings for this table defined as `ReadCapacityUnits=5,WriteCapacityUnits=5` (you'll learn about this in section 12.11).

Execute the following command to create the `todo-user` table with the `uid` attribute as the partition key:

```
$ aws dynamodb create-table --table-name todo-user \                    ①
➥ --attribute-definitions AttributeName=uid,AttributeType=S \          ②
```