⑤ Because only one EC2 instance is running, deploys to all instances at once

⑥ Considers the load balancer's target group when performing deployments

⑦ The IAM role to use for deployments

⑧ The IAM role grants access to autoscaling, load balancing, and other services that are relevant for a deployment.

⑨ Stores the database hostname in the Systems Manager's Parameter Store

By default, CodeDeploy comes with the deployment configurations defined in table 15.1.

Table 15.1 The predefined deployment configurations for CodeDeploy

Name	Description
`CodeDeployDefault.AllAtOnce`	Deploy to all targets at once.
`CodeDeployDefault.HalfAtATime`	Deploy to half of the targets at a time.
`CodeDeployDefault.OneAtATime`	Deploy to targets one by one.

On top of that, CodeDeploy allows you to define your own deployment configurations, such as deploying to 25% of the targets at a time.

After you have deployed and prepared the infrastructure for Etherpad and CodeDeploy, it is about time to create the first deployment. Before you do so, you need to gather some information. Use the following command to get the outputs from the CloudFormation stack named `etherpad-codedeploy`:

```
aws cloudformation describe-stacks --stack-name etherpad-codedeploy \
➥ --query "Stacks[0].Outputs"
```

In our case, the output looks like this: