```
apt-get install -y vector
```

Once installed, you'll need to configure Vector. Vector is configured using a file named `/etc/vector.yaml`. Instructions for a number of services can be found in the Vector documentation.[129]

Run `nano /etc/vector.yaml`, and replace the file with the following:

```
sources:
  docker:
    type: "docker_logs"

sinks:
  nats:
    inputs:
      - "docker"
    type: "console"
    encoding:
      codec: "text"
```

Fill in the definition of the sink based on the service you selected. Exit nano by pressing Ctrl-X, and then press Y to save the file. You can run Vector by running the following command:

```
vector --config vector.yaml
```

Visit your application's website and perform some actions. You should see the logs in your console. Next, edit `/etc/vetor.yaml` once again and replace the definition of the sink based on the service you selected. Finally, give Vector permission to access Docker's information, and start the Vector service:

```
usermod -aG docker vector
systemctl enable vector
systemctl start vector
```

Note that the service you choose can be one that you write yourself. Vector can be used to send logs to Nats,[130] which you can subscribe to in a service that you write yourself. Vector can even be used to send logs to multiple services at once.