Each driver has its own set of custom configuration options.[5] We need to use the --digtialocean-access-token so docker-machine has permission to access and create instances in our account. I've also chosen a region in London (--digitalocean-region lon1) to be close to where I'm located—you can pick a region close to you from the list of regions offered by DigitalOcean.[6]

We've called the new instance do-manager-1, as we're going to use it to act as the manager for our Swarm cluster. You can see that it's now listed if we run:

```
$ docker-machine ls
NAME        ACTIVE DRIVER     STATE   URL        SWARM DOCKER      ERRORS
do-manage… -      digitaloc… Running tcp://46…       v18.09.1
local-vm-1 *      virtualbox Running tcp://19…       v18.09.1
```

Just like with our local VirtualBox instance, we can SSH onto the instance by running docker-machine ssh <instance name>:

```
$ docker-machine ssh do-manager-1
Welcome to Ubuntu 16.04.5 LTS (GNU/Linux 4.4.0-141-generic x86_64)

 * Documentation:  https://help.ubuntu.com
 * Management:     https://landscape.canonical.com
 * Support:        https://ubuntu.com/advantage

  Get cloud support with Ubuntu Advantage Cloud Guest:
    http://www.ubuntu.com/business/services/cloud

18 packages can be updated.
15 updates are security updates.
```

While we're logged in, let's initialize the instance as the swarm manager. To do this, we need to know the instance's internal IP address, which we can find by running:

```
# ifconfig eth0
eth0      Link encap:Ethernet  HWaddr 3a:87:d5:2e:22:9a
          inet addr:46.101.90.10  Bcast:46.101.95.255  Mask:255.255.240.0
          inet6 addr: fe80::3887:d5ff:fe2e:229a/64 Scope:Link
          UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
          RX packets:5519 errors:0 dropped:0 overruns:0 frame:0
          TX packets:3666 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:77351515 (77.3 MB)  TX bytes:359679 (359.6 KB)
```

The IP address is listed on the second line as the inet addr value, which for me is 46.101.90.10, but for you this will differ. Now we can initialize the instance as the swarm manager:

5. https://docs.docker.com/machine/drivers/digital-ocean/#options
6. https://developers.digitalocean.com/documentation/v2/#regions