Listing 4.20 Making Spring Boot Actuator expose the `refresh` endpoint

```
management:
  endpoints:
    web:
      exposure:
        include: refresh    ❶
```

❶ Exposes the /actuator/refresh endpoint through HTTP

NOTE I will discuss Spring Boot Actuator extensively in chapter 13, so don't worry if you don't fully understand the preceding configuration. For now, it's enough to know that Spring Boot Actuator provides many useful endpoints for monitoring and managing applications in production.

The refresh event, `RefreshScopeRefreshedEvent`, will have no effect if there is no component listening. You can use the `@RefreshScope` annotation on any bean you'd like to be reloaded whenever a refresh is triggered. Here's the nice part: since you defined your custom properties through a `@ConfigurationProperties` bean, it is already listening to `RefreshScopeRefreshedEvent` by default, so you don't need to make any changes to your code. When a refresh is triggered, the `PolarProperties` bean will be reloaded with the latest configuration available. Let's see if it works.

CHANGING CONFIGURATION AT RUNTIME

In this final section, I'll show you how to change configuration at runtime. First, make sure you have both the Config Service and Catalog Service up and running (`./gradlew bootRun`). Then open the `config-repo` repository hosting the configuration data and change the value of the `polar.greeting` property in the config-repo/ catalog-service.yml file.

Listing 4.21 Updating the welcome message value in the config repo