(`permittedNumberOfCallsInHalfOpenState`). If at least 50% of them result in an error, the circuit will go back to the open state. Otherwise, the circuit breaker will trip to the closed state.

On to the code. In the Edge Service project (edge-service), at the end of the application.yml file, define a default configuration for all Resilience4J circuit breakers.

Listing 9.8 Configuring circuit breaker and time limiter

```
resilience4j:
  circuitbreaker:
    configs:
      default:                                          ❶
        slidingWindowSize: 20                           ❷
        permittedNumberOfCallsInHalfOpenState: 5        ❸
        failureRateThreshold: 50                        ❹
        waitDurationInOpenState: 15000                  ❺
  timelimiter:
    configs:
      default:                                          ❻
        timeoutDuration: 5s                              ❼
```

❶ Default configuration bean for all circuit breakers

❷ The size of the sliding window used to record the outcome of calls when the circuit is closed

❸ Number of permitted calls when the circuit is half-open

❹ When the failure rate is above the threshold, the circuit becomes open.

❺ Waiting time before moving from open to half-open (ms)

❻ Default configuration bean for all time limiters

❼ Configures a timeout (seconds)

We configure both the circuit breaker and a time limiter, a required component when using the Resilience4J implementation of Spring Cloud Circuit Breaker. The timeout configured via Resilience4J will take precedence over the response timeout we defined in the previous section for the Netty HTTP client