Constructs a new `std::condition_variable_any` instance.

Throws

An exception of type `std::system_error` if the condition variable couldn't be constructed.

Std::Condition_Variable_Any Destructor

Destroys a `std::condition_variable_any` object.

Declaration

```
~condition_variable_any();
```

Preconditions

There are no threads blocked on `*this` in a call to `wait()`, `wait_for()`, or `wait_until()`.

Effects

Destroys `*this`.

Throws

Nothing.

Std::Condition_Variable_Any::Notify_One Member Function

Wakes one of the threads currently waiting on a `std::condition_variable_any`.

Declaration

```
void notify_one() noexcept;
```