Note

This is an atomic read-modify-write operation for the memory location comprising `*this`.

Std::Atomic_Fetch_Add Nonmember Function

Atomically reads the value from an `atomic<`*integral-type*`>` instance and replaces it with that value plus the supplied value `i`.

Declaration

```
integral-type  atomic_fetch_add(
    volatile atomic<integral-type>* p, integral-type i) noexcept;
integral-type  atomic_fetch_add(
    atomic<integral-type>* p, integral-type i) noexcept;
```

Effects

```
return p->fetch_add(i);
```

Std::Atomic_Fetch_Add_Explicit Nonmember Function

Atomically reads the value from an `atomic<`*integral-type*`>` instance and replaces it with that value plus the supplied value `i`.

Declaration

```
integral-type  atomic_fetch_add_explicit(
    volatile atomic<integral-type>* p, integral-type i,
    memory_order order) noexcept;
integral-type  atomic_fetch_add_explicit(
    atomic<integral-type>* p, integral-type i, memory_order order)
    noexcept;
```

Effects

```
return p->fetch_add(i,order);
```

Std::Atomic<Integral-Type>::Fetch_Sub Member Function