


Figure 7.3 Priority of the configuration fallback structure. The highest priority is at the top and overrides definitions in lower files.

By default, the file application.{conf,json,properties} is used to read the configuration. There are two ways to change the name of the configuration file. The first option is to use an overloaded `load` function on the `ConfigFactory`. When loading the configuration, supply the name of the base:

```
val config = ConfigFactory.load("myapp")   ❶
```

❶ Requests that the configuration factory load the file myapp.{conf,json,properties}