```
    sslContext.init(null, tmf.getTrustManagers(), null);
#D

    this.httpClient = HttpClient.newBuilder()
            .sslParameters(sslParams)    #E
            .sslContext(sslContext)     #E
            .build();

} catch (GeneralSecurityException | IOException e) {
    throw new RuntimeException(e);
}
```

#A Only allow TLS 1.2 or TLS 1.3.
#B Configure secure cipher suites for TLS 1.3…
#C …and for TLS 1.2.
#D The SSLContext should be configured to only trust the CA used by your AS.
#E Initialize the HttpClient with the chosen TLS parameters.

7.4.3 Token revocation

Just as for token introspection, there is an OAuth2 standard for revoking an access token (https://tools.ietf.org/html/rfc7009). While this could be used to implement the `revoke` method in the `OAuth2TokenStore`, the standard only allows the client that was issued a token to revoke it, so the RS (the Natter API in this case) cannot revoke a token on behalf of a client. Clients should directly call the AS to revoke a token, just as they do to get an access token in the first place.

Revoking a token follows the same pattern as token introspection: the client makes a POST request to a