- A moderator can read posts and delete offensive posts.
- A normal member can read and write posts, but not delete any.
- An observer is only allowed to read posts and not write their own.

Open src/main/resources/schema.sql in your editor and add the lines from listing 8.5 to the end of the file and click save. You can also delete the existing `permissions` table (and associated `GRANT` statements) if you wish.

Listing 8.5 Role permissions for the Natter API

```
CREATE TABLE role_permissions(    #A
    role_id VARCHAR(30) NOT NULL PRIMARY KEY,    #A
    perms VARCHAR(3) NOT NULL    #A
);
INSERT INTO role_permissions(role_id, perms)
    VALUES ('owner', 'rwd'),    #B
           ('moderator', 'rd'),    #B
           ('member', 'rw'),    #B
           ('observer', 'r');    #B
GRANT SELECT ON role_permissions TO natter_api_user;    #C
```

#A Each role grants a set of permissions.
#B Define roles for Natter social spaces.
#C As the roles are fixed, the API is granted read-only access.

> **MINI-PROJECT** Some RBAC systems allow roles to inherit from other roles, so that changes in permissions assigned to the parent role are