Listing 8.6 Static role mappings

```
CREATE TABLE user_roles(    #A
    space_id INT NOT NULL REFERENCES spaces(space_id),    #A
    user_id VARCHAR(30) NOT NULL REFERENCES
users(user_id),    #A
    role_id VARCHAR(30) NOT NULL REFERENCES
role_permissions(role_id),    #A
    PRIMARY KEY (space_id, user_id)    #B
);
GRANT SELECT, INSERT, DELETE ON user_roles TO
natter_api_user;    #C
```

#A Map users to roles within a space.
#B Natter restricts each user to have only one role.
#C Grant permissions to the Natter database user.

To grant roles to users you need to update the two places where permissions are currently granted inside the `SpaceController` class:

- In the `createSpace` method the owner of the new space is granted full permissions. This should be updated to instead grant the `owner` role.
- In the `addMember` method, the request contains the permissions for the new member. This should be changed to accept a role for the new member instead.

The first task is accomplished by opening the SpaceController.java file and finding the line inside the `createSpace` method where the insert into the permissions table statement is. Remove those lines and replace them instead with the following to insert a new role assignment: