```
    sha256sum -b -c $RELEASE.sha256 && \    #B
    unzip $RELEASE && rm -f $RELEASE    #C

FROM gcr.io/distroless/java:11    #D
WORKDIR /opt    #D
COPY --from=build-env /tmp/h2/bin /opt/h2    #D

USER 1000:1000    #E

EXPOSE 9092    #F
ENTRYPOINT ["java", "-Djava.security.egd=file:/dev/urandom",
\    #G
        "-cp", "/opt/h2/h2-1.4.197.jar", \    #G
        "org.h2.tools.Server", "-tcp", "-tcpAllowOthers"]
#G
```

#A Define environment variables for the release file and hash.
#B Download the release and verify the SHA-256 hash.
#C Unzip the download and delete the zip file.
#D Copy the binary files into a minimal container image.
#E Ensure the process runs as a non-root user and group.
#F Expose the H2 default TCP port.
#G Configure the container to run the H2 server.

Linux users and UIDs

When you log in to a Linux operating system (OS) you typically use a string username such as “guest” or “root”. Behind the scenes, Linux maps these usernames into 32-bit integer UIDs (user IDs). The same happens with group names, which are mapped to integer GIDs (group IDs). The mapping between usernames and UIDs is done by the /etc/passwd file, which can differ inside a container from the host OS. The root user always has a UID of 0[1]. Normal users usually have UIDs starting at 500 or 1000. All permissions to access files and other resources are determined by the operating system in terms of UIDs and GIDs rather than user and group names, and a process can run with a UID or GID that doesn’t correspond to any named user or group.

By default, UIDs and GIDs within a container are identical to those in the host. So UID 0 within the container is the same as UID 0 outside the container; the root user. If you run a