```
ByteBuffer.allocate(session.getApplicationBufferSize());
#B
```

#A Retrieve the SSLSession from the engine
#B Use the session hints to correctly size the data buffers

Data is moved between buffers by using the following two method calls, also illustrated in figure 12.2:

- `sslEngine.wrap(appData, sendBuf)` causes the `SSLEngine` to consume any waiting application data from the `appData` buffer and write one or more DTLS packets into the network `sendBuf` that can then be sent to the other party.
- `sslEngine.unwrap(recvBuf, appData)` instructs the `SSLEngine` to consume received DTLS packets from the `recvBuf` and output any decrypted application data into the `appData` buffer.