#D In the NEED_UNWRAP state you should wait for a network packet if not already received
#E Let the switch statement fall through to the NEED_UNWRAP_AGAIN case
#F Process any received DTLS packets by calling engine.unwrap()
#G Check the result status of the unwrap() call and update the handshake state
#H In the NEED_WRAP state call the wrap() method and then send the resulting DTLS packets
#I For NEED_TASK, just run any delegated tasks or submit them to a thread pool

The `wrap()` and `unwrap()` calls return a status code for the operation as well as a new handshake status, which you should check to ensure that the operation completed correctly. The possible status codes are shown in table 12.1. If you need to resize a buffer, you can query the current `SSLSession` to determine the recommended application and network buffer sizes and compare that to the amount of space left in the buffer. If the buffer is too small you should allocate a new buffer and copy any existing data into the new buffer. Then retry the operation again.

Table 12.1 SSLEngine operation status codes

Status code	Meaning
`OK`	The operation completed successfully.
`BUFFER_UNDERFLOW`	The operation failed because there was not enough input data. Check that the input buffer has enough space remaining. For an unwrap operation you should receive another network packet if this status occurs.
`BUFFER_OVERFLOW`	The operation failed because there wasn't enough space in the output buffer. Check that the buffer is large enough and resize it if necessary.
`CLOSED`	The other party has indicated that they are closing the connection, so you should process any remaining packets and then close the `SSLEngine` too.