```
import java.net.*;
import java.security.*;
import org.bouncycastle.tls.*;
import org.bouncycastle.tls.crypto.impl.bc.BcTlsCrypto;

public class PskServer {
    static byte[] loadPsk(char[] password) throws Exception {
        var keyStore = KeyStore.getInstance("PKCS12");    #A
        keyStore.load(new FileInputStream("keystore.p12"),
password);    #A
        return keyStore.getKey("hmac-key",
password).getEncoded();    #B
    }
}
```

#A Load the keystore
#B Load the key and extract the raw bytes

Listing 12.9 shows a basic DTLS server with pre-shared keys written using the Bouncy Castle API. The following steps are used to initialize the server and perform a PSK handshake with the client:

- First load the PSK from the keystore.
- Then you need to initialize a `PSKTlsServer` object, which requires two arguments: a `BcTlsCrypto` object, and a `TlsPSKIdentityManager` that is used to lookup the PSK for a given client. You'll come back to the identity manager shortly.
- The `PSKTlsServer` class only advertises support for normal TLS by default, although it supports DTLS just fine; override the `getSupportedVersions()` method to ensure that DTLS 1.2 support is enabled, otherwise the handshake will fail. The supported protocol versions