```
$ sudo systemctl start httpd
$ sudo systemctl enable httpd
```

To access the default website served by Apache, you need to know the public IPv4 address of your EC2 instance. Get this information by selecting your virtual machine and looking into the details via the Management Console. You can also execute the following command in the terminal of your EC2 instance:

```
$ curl http://169.254.169.254/latest/meta-data/public-ipv4
```

Open http://$PublicIp in your browser. Don't forget to replace `$PublicIp` with the public IPv4 address of your EC2 instance, for example, http://52.54.202.9. A demo website appears.

The public IPv4 address assigned to your EC2 instance is subject to change. For example, when you stop and start your instance, AWS assigns a new public IPv4 address. Therefore, you will learn how to attach a fixed public IP address to the virtual machine in the following section.

3.6 Allocating a public IP address

You've already launched some virtual machines while reading this book. Each VM was connected to a public IP address automatically. But every time you launched or stopped a VM, the public IP address changed. If you want to host an application under a fixed IP address, this won't work. AWS offers a service called *Elastic IPs* for allocating fixed public IP addresses.

Using a fixed public IP address is useful, in case clients aren't able to resolve a DNS name, a firewall rule based on IP addresses is required, or you don't want to update DNS records to avoid the delay until all clients resolve to the new IP address. Therefore, allocate a public IP address and associate with your EC2 instance named `sydney` as follows: