```
    - !Ref SubnetB
    Tags:
    - PropagateAtLaunch: true
      Value: etherpad
      Key: Name
  CreationPolicy:
    ResourceSignal:
      Timeout: PT10M
  UpdatePolicy:                                    ⑤
    AutoScalingRollingUpdate:                      ⑥
      PauseTime: PT10M                             ⑦
      WaitOnResourceSignals: true                  ⑧
      MinInstancesInService: 1                     ⑨
```

① The resource defines the Auto Scaling group.

② References the launch template we saw earlier

③ Etherpad does not support clustering; therefore, we are launching a single machine.

④ To enable zero-downtime deployments, we must launch a second machine during the deployment process.

⑤ The update policy specifies the behavior of CloudFormation in case of changes to the launch template.

⑥ That's where the magic happens: the configuration of the rolling update.

⑦ The Auto Scaling group awaits a success signal from launching the EC2 instance within 10 minutes (see cfn-signal in user data script).

⑧ The Auto Scaling group waits for a signal from the EC2 instance.

⑨ Makes sure the instance is up and running during the update to ensure zero downtime deployment

Let's make the update from version 1.8.17 to 1.8.18 happen. Execute the following command to update the CloudFormation stack. You might want to open the AWS Management Console and watch the running EC2 instances. CloudFormation will spin up a new EC2 instance. As soon as the new EC2 instance is ready, CloudFormation will terminate the old one:

```
$ aws cloudformation deploy --stack-name etherpad-cloudformation \
➥ --template-file cloudformation.yaml \
```