- You can create an `IHostBuilder` by calling `Host.CreateDefaultBuilder()`. This creates a `HostBuilder` instance using the default configuration, similar to the configuration used when calling `WebApplication.CreateBuilder()`. The default `HostBuilder` uses default logging and configuration providers, configures the hosting environment based on environment variables and command-line arguments, and configures the DI container settings.
- ASP.NET Core apps using the generic host typically call `ConfigureWebHostDefaults()`, on the `HostBuilder`, providing a lambda that calls `UseStartup<Startup>()` on an `IWebHostBuilder` instance. This tells the `HostBuilder` to configure the DI container and middleware pipeline based on the `Startup` class.
- Use the `Startup` class to register services with DI, configure your middleware pipeline, and register your endpoints. It is a conventional class, in that it doesn't have to implement an interface or base class. Instead, the `IHostBuilder` looks for specific named methods to invoke using reflection.
- Register your DI services in the `ConfigureServices(IServiceCollection)` method of `Startup`. You register services using the same `Add*` methods you use to register services on `WebApplicationBuilder.Services` when using minimal hosting.