You can create a new scope by calling `CreateScope()` or `CreateAsyncScope()` on `IServiceProvider`, which returns a disposable `IServiceScope` object, as shown in figure 9.13. `IServiceScope` also exposes an `IServiceProvider` property, but any services resolved from this provider are disposed of automatically when you dispose the `IServiceScope`, ensuring that all the resources held by the scoped and transient services are released correctly.




Figure 9.13 To resolve scoped or transient services manually, you must create an `IServiceScope` object by calling `CreateScope()` on