


Figure 5.8 X-Powered-By response header

The Access-Control-Allow-Headers header is used by the preflight to indicate which headers are allowed on the request. The Access-Control-Expose-Headers header is used by the actual response to indicate which response headers are visible to the client.

The following listing adds the Access-Control-Expose-Headers header to the server. Once this is included in the response, the X-Powered-By header will be visible to the `getResponseHeader` method.

Listing 5.6 Adding the Access-Control-Expose-Headers header

```
var handleCors = function(req, res, next) {
  res.set('Access-Control-Allow-Origin', 'http://localhost:1111');
```