Table 4. Informix Slob Modes

Value	Informix API Constant
1	LO_RDONLY
2	LO_WRONLY
4	LO_APPEND
8	LO_RDWR
16	LO_BUFFER
32	LO_NOBUFFER

boolean ifxus_free_slob(integer slob)

The ifxus_free_slob function deletes a slob object.

integer ifxus_open_slob(integer slob, integer mode)

Use ifxus_open_slob to get an identifier for an existing slob object. The modes listed in Table 4 may be combined with | operators.

string ifxus_read_slob(integer slob, integer bytes)

The ifxus_read_slob function returns data from the specified slob object. The bytes argument specifies the number of bytes to return.

integer ifxus_seek_slob(integer slob, integer mode, integer offset)

The ifxus_seek_slob function moves the current cursor position within a slob object. The mode argument controls where the offset is applied. If mode is 0, offset is applied to the beginning. If mode is 1, offset is applied to the current position. If mode is 2, offset is applied to the end of the slob object.

integer ifxus_tell_slob(integer slob)

The ifxus_tell_slob function returns the current position of a cursor inside a slob object.

integer ifxus_write_slob(integer slob, string data)

The ifxus_write_slob function writes data to an open slob object. The number of bytes written is returned.