boolean ibase_commit(integer link)

The ibase_commit function commits the default transaction on the specified link, or the last link if none is specified.

integer ibase_connect(string path, string user, string password)

Use ibase_connect to connect to an InterBase database. You must specify a path to database file. The user and password arguments may be omitted. They default to those set in php.ini using the ibase.default_user and ibase.default_password directives.

A connection identifier is returned that is used by most of the other functions. When the script ends, the connection will be closed for you, but you can close it manually with ibase_close. A second connection attempt to the same database as the same user will return the same connection identifier.

Compare this function to ibase_pconnect.

string ibase_errmsg()

Use ibase_errmsg to get the last error message. FALSE is returned when no error message is available.

integer ibase_execute(integer query, value bind, ...)

Use ibase_excute to execute a query prepared with ibase_prepare. If the query contained ? placeholders, you must supply matching bind values following the query identifier. A result identifier is returned if executing a select query.

object ibase_fetch_object(integer result, integer blob)

The ibase_fetch_object function returns an object that contains a property for each column in the next result row. The name of the property will match the name of the column. The blob argument is optional. If set to IBASE_TEXT, blob columns will be returned as text. Otherwise the blob identifier is returned. FALSE is returned when no rows remain.

array ibase_fetch_row(integer result, integer blob)

The ibase_fetch_row function operates identically to ibase_fetch_object except that an array is returned. Instead of being referenced by name, columns are referenced by number, starting with 0.