```
        //undo the inserts
        //Normally, you won't do this, if we undo the inserts
        //each time, we can run the example over and over
        ocirollback($Connection);

        //close connection
        ocilogoff($Connection);
?>
```

boolean ocicancel(integer statement)

The ocicancel function fetches the next row from a statement. Internally it calls the OCIStmtFetch function, which is part of OCI, specifying zero for the number of rows. In every other way, it is identical to ocifetch.

boolean ocicolumnisnull(integer statement, value column)

Use ocicolumnisnull to test whether a column is null. You may specify columns by number, in which case columns are numbered starting with 1, or you may specify columns by name.

string ocicolumnname(integer statement, integer column)

The ocicolumnname function returns the name of a column given the column number. Columns are numbered starting with 1.

integer ocicolumnsize(integer statement, value column)

The ocicolumnsize function returns the size of a column. You may specify columns by number, in which case columns are numbered starting with 1, or you may specify columns by name

value ocicolumntype(integer statement, integer column)

Use ocicolumntype to get the type of the specified column. You may specify columns by number, in which case columns are numbered starting with 1, or you may specify columns by name. The name of the type will be returned if it is one of the following: BFILE, BLOB, CHAR, CLOB, DATE, LONG RAW, LONG, NUMBER, RAW, REFCURSOR, ROWID, VARCHAR. Otherwise, an integer code from the data type will be returned.

boolean ocicommit(integer connection)

The ocicommit function commits all previous statements executed on the connection. By default, statements are committed when executed. You can override this functionality when you call ociexecute, by specifying a mode.