



Linux

+ The X Drivers

I have a P-III, on an Intel 810 chipset. I tried installing Linux (Red Hat 6.2), but am not able to configure my monitor, because of which I am not able to run my X, both KDE and Gnome. Please solve my problem.

Dipin Gaba

Via e-mail

R The problem is due to the graphics card and not the monitor. Linux, by default, does not support the Intel 810 motherboard's internal graphics card. However, once the right drivers are installed, the problem will be solved. Visit the following link to install the latest drivers:

<http://support.intel.com/support/graphics/intel810/>

Alternately, you can also configure the Intel 810 graphics controller in Linux, if you have the AGP GART module in your kernel. This is required, as there is no dedicated video memory on an Intel 810 card.

Download the latest kernel from www.redhat.com/errata; this will include the AGP GART module. Next, run the following command in the terminal,

```
ls /lib/modules/`uname -r`/misc/agpgart.o
```

You can now configure X by running Xconfigurator. Select the i810 video card. Select the correct monitor or use Custom to specify the monitor's settings. Select 4096 as the amount of video RAM when asked. Also make sure that Linux has detected the correct amount of system RAM. You can verify this by using any of the following commands:

```
# cat /proc/meminfo
# top
```

If the RAM is lesser than the actual RAM in your system, then you may need to edit the `/etc/lilo.conf` to allow Linux to recognise the exact RAM in your system. Open `/etc/lilo.conf` in one of the text editors, and add the line, `append="mem=127M"`, to the bottom of the image section, assuming you actually have 128 MB of RAM, which the system has not detected. Note

Troubleshooting

Problems with boot up in Windows 95, error when viewing TV through a PC-TV card, invalid page fault in IE 5, removing additional Startup entries...solutions to these and other problems

```
boot=/dev/hda
map=/boot/map
install=/boot/boot.b
prompt
timeout=50
message=/boot/message
linear
default=linux

image=/boot/vmlinuz-2.2.16-22
label=linux
read-only
root=/dev/hda1
append="mem=127M"
```

Editing lilo to get the exact amount of RAM recognised

that 1 MB of RAM should be subtracted from the actual amount of RAM that you have. After editing the `lilo.conf` file, run the command, `/sbin/lilo`. This will now enable lilo to detect the RAM in your system.

Internet & Communications


+ Deleting unwanted URLs

How can I selectively clear URLs from my IE's address drop-down list?

Gaurav

Via e-mail

R To selectively clear URLs, you can either edit the registry, or use software that



Selectively removing URLs from IE's drop-down list

allows you to do so. Remember to back up your registry before editing it. Here's what you should do:

Make sure that your IE is not running. Then go to Start > Run. Type `regedit` and click OK. Navigate to `HKEY_CURRENT_USER\Software\Microsoft\Internet Explorer\Typed URLs\`.

The URLs will be visible in the drop-down list. Just select the ones that you do not need and delete them. Exit the registry and restart Windows. The URLs will no longer be visible in the drop-down list.

Windows

+ No safe mode

I cannot start my PC in Safe mode. Whenever I choose Safe mode from the Windows boot menu, I get the following message: 'error:HIMEM SYS has detected unreliable XMS memory address <some_address> XMS driver not installed.'

Prashant Shetty

Via e-mail

R The error is usually caused by a fault in the computer's external cache controller or by bad or mismatched memory chips. You should try the following:

Disable external cache, which is also known as secondary cache or CPU cache in BIOS. Check whether the RAM modules in the system fit properly in the slots. Make sure that the RAM type and speed are compatible.

Internet & Communications

+ Cannot connect automatically

I recently reinstalled Windows 98 SE on my computer. Now in my Dial-up Networking I don't find the option to Connect Automatically. I use IE 5.5. Please advice.

Sarshad

Via e-mail

R The Connect Automatically option does not come in Dial-up Networking, but is a feature of the Internet Explorer →