


with Sticpl.cpl is displayed. Recently I had downloaded and installed the Windows 98 Q323255 Update. Could this have caused the problem?

Nitesh Kumar Jain

Via e-mail

A It seems that the Stimon.exe file on your PC is damaged. Press [Ctrl] + [Alt] + [Del] and check if Stimon is running. If it is, end the task. Delete the file from \Windows\System. Run the Registry Editor and navigate to HKEY_Local_Machine\Software\Microsoft\Windows\CurrentVersion. Look for a value named StillImageMonitor under either the Run or RunServices keys. Delete the value and restart the PC. Now reinstall the drivers for the USB camera.



Restoring a file using System File Checker

If you still get an error, replace the Sticpl.cpl file, too. To do this, run sfc from **Start > Run** and insert the Windows 98 installation disk. Select the option 'Extract one file from installation disk' and click Browse. Locate Sticpl.cpl in the \Windows\System folder and click Start. Restart the machine after restoring the file.

Bootable floppy

Q I made a bootable disk several times, using different floppies, but my PC doesn't boot from it. I can see the file list on the disk from DOS and Windows. What could be the problem?

Ashish

Via e-mail


A Your PC is probably not set to boot from the floppy drive. This is a setting in the BIOS, where you can choose what device chain it should look through for booting. While the PC is booting, press the [Delete] key ([F2] on some BIOSes) to enter the BIOS setup. The way to access this option varies across different BIOSes, but just look for an option such as Boot

Installing Solaris

Q I have a Compaq Presario PC with Windows XP pre-installed on it. The partitions of my 40 GB hard disk are 37 GB (NTFS) and 2.7 GB (FAT32). I want to install Solaris 8 on my machine. When I boot the Solaris kernel, it gets terminated and the system gets restarted. Is there a problem with my BIOS, which is not allowing the kernel to run on it?

Gaurav

Via e-mail



ILLUSTRATIONS: Mahesh Benkar

A The installer is probably having some problems with the 40 GB hard

disk. The OS does not support disks beyond 32 GB, as documented on the Sun Web site. Your BIOS probably does support the drive, as Windows XP is installed and running on it. One workaround to this is to get another smaller hard disk and install Solaris on it, install the patches for Solaris that enable support for large disks, then reconnect the 40 GB drive. Another possible workaround is to install Solaris 8 on a smaller hard disk and then connect the 40 GB drive, but disable it in the BIOS. You could also try setting the drive to 32 GB in the BIOS and installing the operating system.

Order or First Boot Device. Ensure that A or Floppy is set as the first boot device, save the changes and exit the BIOS. Henceforth, it should boot from the floppy. If it still doesn't, the problem could be with the floppy drive itself, in which case you will have to get it replaced.

Running old programs

Q I need to run a DOS accounting software under Windows Me, but I have to change the Files variable to 100, which by default is 10. In Windows 98, I used to set it from the config.sys file, but in Windows Me I cannot edit it. How can this be done?

Rahil Mehta

Via e-mail

A You can set the environment variable from the autoexec.bat file instead of the config.sys file. Use the DOS command **SET** to assign a value to a variable. Thus, you can enter the following line in the autoexec.bat file, or type it directly at the Command Prompt:

SET FILES=100

To remove an environment variable, type the **SET** command without any value (**SET FILES=**) and simply type **SET** to view a list of current variables.

Receipt confirmation


Q I have a Pentium II 433 MHz system with 128 MB RAM running Windows 98 SE. I have Outlook Express 6 installed as my e-mail client. How can I confirm that the person to whom the mail has been

sent has seen the message?

Sukhbir

Via e-mail

A You can request a notification when the recipient reads the message using the Request Read Receipt option in Outlook Express. When creating a message, click **Tools > Request Read Receipt** to enable this for the message. A better option would be to enable this permanently, so that the request goes with every message you send. To do this, open **Tools > Options > Receipts** and enable 'Request a read receipt for all sent messages'. Here, you will also notice how Outlook Express should respond to receipt requests it gets from other senders. When the recipient first opens your message or views it in the Preview Pane,



Enable Read Receipt requests in Outlook Express