




The status section in SWAT lets you check the status of the Samba server

Daemon), and CUPS (Common UNIX Printing System).

Finally, check the Samba server's status in the Status section. It provides a button to start, stop or restart the server.

4 Install and manage printers using CUPS

CUPS provides a portable printing layer for UNIX-based operating systems. Most of the newer distributions bundle CUPS along. You can also download it at <http://public.planetmirror.com/pub/cups/1.1.4/>. Once you've downloaded CUPS, remove your old printing software. Then, install CUPS by typing: `rpm -ivh cups-1.1.4-linux-2.2.14-intel.rpm`.

Note that your filename may differ slightly. By default, CUPS installs with a Web-based, and console-based interface. It should start automatically when installed via RPM. To verify whether the cupsd daemon is running, execute the following, with the privileges of the root user: `/etc/rc.d/init.d/cups status`

If you receive 'cups: Scheduler is running' as the output message, you are ready to explore the Web interface.

If not, start the scheduler, by typing `/etc/rc.d/init.d/cups start`, with root privileges.

Once the CUPS scheduler is running,



The default CUPS screen provides you with online help

point your Web browser to <http://localhost:631/>. The :631 tells your browser to connect to port 631, instead of the standard Web port 80.



Clicking on 'Do Administrative Tasks', brings up the Admin screen

There will be a variety of options in your browser. Click on the first one—Do Administration Tasks—and you will be prompted to log in. Log in as root, using your root password, and the Admin screen will come up.

Although the 'Class and Jobs' section appears ahead of Printer, we will add the printer first. Press the Add Printer button, and you will be asked for printer name, host name and the printer's description.

Next, specify the device, device Uniform Resource Identifier (URI), make and model for the printer, one after the



The printer setup process lets you choose the model number

other. The file option lets you print directly to a file on the hard drive. The http option lets you print directly to the CUPS port. The ipp option lets you print to a queue with the Internet Printing Protocol. The smb option lets you print to shared printers, connected to a Windows PC—if you use Windows as a print server. If the printer is locally connected, specify the port to which the printer is connected. Once you furnish all these

BONUS TIP 3

Uncompress packages

Here's how to install a .tar file.

Execute the following command:

`tar -xvf <package>.tar`

This creates a folder by the name <package> and extracts the files in it. Next, change the current working directory to the <package> directory (using `cd <package>`), and compile the file again. To compile first you need to execute the `./configure` command.

Now, create a binary file that can be executed, with the help of the `make` command, and then install the compiled program, using the `make install` command.

The normal process to install <package>.tar.gz, and <package>.tar differs only by a step. The <package>.tar.gz file is first converted to <package>.tar file, and then the normal process of installing



Type in the device URI in the Admin screen

the tar files is followed. Converting the .tar.gz file to .gz can be achieved, using the command: `gunzip <package>.tar.gz`.

An alternative method is to combine both commands (`gunzip <package>.tar.gz` and `tar -xvf <package>.tar`) to a single command line:

`tar -zxvf <package>.tar.gz`

You can even execute the same command, using pipes, as follows:

`gunzip <package>.tar.gz | tar -xvf`

details, your printer set up is complete. Now, you can manage printers, classes, as well as print jobs.

The Classes option allows you to place a series of printers into a pool, or class. If you print to a class, instead of a specific printer, the first available printer in the class will receive the job. This is useful if you do a lot of high-production printing, and have a series of printers at a central location.