



Displaying the Multi Camera Monitor

Multi-camera monitor plays footage of each camera and a preview of the final edited sequence. After recording the final sequence, camera preview makes it active and record footage from that camera. In playback mode, the active camera is indicated by a yellow border and red while recording. This monitor includes the controls for standard playback and transport. The sequence in the preview display can be played using the play around button (⏮) including any pre- or post-

edge or corner. In multi camera mode, you can use a few handy keyboard shortcuts such as Spacebar to pause / resume the preview, [J] to run the preview backwards, [K] to stop the preview, and L to run the preview forward.

Adding clips for multi-camera editing

You can use any type of media in multi-camera editing session, including footage from various cameras or still images. The media can be assembled into sequences of up to four videos and four audio tracks

attempting to synchronise them. Sync points can be marked by setting similarly numbered markers for each clip or setting the time code manually for the clip, as was done in the assembly of the clips. Avoid overwriting adjacent clips if you have multiple clips on the same track.

Select the clips to be synchronised and target a track by clicking its track header to align other clips to it. If synchronisation is by the in-point, the beginning of each clip aligns with the in-point of the target track. If the in-point falls before the point


according to the out points of the clips.

- Time code synchronizes by a specified timecode. To make this less cumbersome, video editing professionals choose to use only minutes, seconds and frames to synchronize the clips. This can be done by selecting the ignore hours option.
- Numbered clip marker synchronizes by the assigned markers placed on the clip.

Creating multi camera target / nested sequence

Create a new sequence from the file menu and drag the sequence with the multi-camera clips into one of the video tracks on the new sequence. This is nesting of a sequence. Sequences can be nested within sequences to innumerable depths in order to create diverse groups and structure. Multi-camera can be enabled for selected clips by enabling it in the clip menu. Nested sequences appear as single clip even though the source may contain multiple tracks. Operations such as moving, trimming and applying effects to a nested sequence is similar to any other clip. Changes in source sequence are automatically applied to the nest. Nesting enables a video editor to repeat complex sequences without the necessity of reworking the entire set of effects and operations. Playing same sequence with different effect at each playback. Reduce the estate used on the editing menu and keeps the workspace primp and neat, and hence reducing any possibility of losing sync during editing.

Apply new transition to each clip in the nest, which in case of clips can be done for only one transition. A sequence, however, cannot be nested within itself and nesting takes up more processing time



Multi-Camera Monitor workspace

roll frames.

To display the Multi-Camera Monitor, select the multi-camera target sequence in the timeline panel and then choose the multi-camera monitor from the window menu. Disable the show preview monitor from Multi-Camera monitor panel menu to display only camera previews (and hide the recorded sequence preview). The multi-camera monitor can be resized by dragging any

and you can add more than one clip to a track if required. Upon assembly of clips, synchronise them and create the target sequence by firstly creating a new sequence and placing clips from each camera on a separate video (and audio) track. Only one clip per track can be synchronised.

Synchronising clips

Mark the sync points for each camera's footage before

zero, the clip will be trimmed accordingly during synchronization. If a track of the linked video/audio pair is unselected, the pair becomes out of sync, and out-of-sync indicators will appear on the clips.

Choose Synchronize from the Clip menu and select among:

- Clip Start synchronizes clips according to the in points of the clips.
- Clip End synchronizes clips