

due to the possibility of long references. Nested sequence changes on any change made to the contents of the nest, however the duration and timecode is not affected. Empty spaces at the beginning (not end) of a source sequence determines the start point of the nested sequence. Editing a nested sequence does not require re-rendering of the clips. Source of nested sequences can be opened by double-clicking on the nested sequence.


Recording multi-camera edits

Open the multi camera monitor for a multi-cam sequence and click the button for record on/off (⏻). To enable recording during playback, click preview of the camera you want to record on the multi-camera monitor. Selecting Audio follows Video in the multi-camera panel menu, enables recording audio from the selected camera. Mix the desired tracks to one track on the source sequence, and select the resulting audio to record audio from the selected camera to the audio track (Audio follows video option must be disabled in this case).

The playback button plays video from all the cameras, and the footage from active camera is recorded in the target sequence of multi-camera. You can switch between cameras by selecting the particular preview or hitting the corresponding keyboard number key (for example, 1 for camera 1).

The stop or the record button releases the recording mode. Playback controls can be used for preview after the recording stops. This does not overwrite the recorded sequence. Effects recorded in a target sequence are not displayed in the multi-camera monitor preview. For viewing with effects, play the track in the program monitor.

To re-record multi-camera edits, the current time indi-



Before clicking on the Record, the selected clip has Yellow Border



After clicking on the Record, the selected clip has Red Border

cator must be positioned before the edit requiring adjustment. Run the multi-camera monitor preview, and change the active camera by clicking on the desired camera, whence the yellow selection turns red, indicating a record enabled status. The editing can be stopped by hitting the stop playback button.

Adjusting / refining multi camera edits

You can replace clips with other footages by simply replacing the clip on the timeline panel

with the new footage. In some cases you may need to swap between different views of a scene taken from different cameras, such clips can be overlayed or inserted in the multi camera sequence. This can be done by double clicking on the target sequence in the timeline which opens it in the source monitor which displays footage previews of original clips. Select the display for the footage to be added to the sequence (on select, the display border is in yellow) and choose the source you want to modify

and drag the clip to the timeline. You can also use the insert (⌘+I) or overlay (⌘+O) buttons in the source monitor for the same purpose.

Adding transitions

You would like to add some transitions like colour correction, adding titles and green screen overlays to your clips. Video and audio transitions can be added by using the shortcuts to add the default transition for both audio and video. Roll the current time indicator on the timeline to the beginning and