

<code>parameter /= value</code>	Integer division. Equivalent to <code>parameter = parameter / value</code> .
<code>parameter %= value</code>	Modulo. Equivalent to <code>parameter = parameter % value</code>
<code>parameter++</code>	Variable post-increment. Equivalent to <code>parameter = parameter + 1</code>
<code>parameter--</code>	Variable post-decrement. Equivalent to <code>parameter = parameter - 1</code> .
<code>++parameter</code>	Variable pre-increment. Equivalent to <code>parameter = parameter + 1</code> .
<code>--parameter</code>	Variable pre-decrement. Equivalent to <code>parameter = parameter - 1</code> .

Here increment (`++`) and decrement (`--`) operators are used to either increase or decrease the given value of the parameters by one respectively. Their placement has a minor difference in the original value. If they are placed in front of the parameter, the value is changed before the parameter is returned while if they are placed after, the operation takes place after the parameter is returned.

- `[me@linuxbox ~]$ foo=3`
- `[me@linuxbox ~]$ echo $((foo++))`
- `3`
- `[me@linuxbox ~]$ echo $foo`
- `4`

- `[me@linuxbox ~]$ foo=1`
- `[me@linuxbox ~]$ echo $((++foo))`
- `2`
- `[me@linuxbox ~]$ echo $foo`
- `2`

Bit Operators

Bit operators are used for low-level tasks such as reading bit-flags or settings.

OPERATOR	DESCRIPTION
<code>~</code>	Bitwise negation
<code><<</code>	Left bitwise shift. Shift all the bits in a number to its left.