

and writing the devices by adding the line:

```
/etc/devfs.rules.
```

Note: If the internal SCSI discs are installed in the main system, you can alter the second line as:

```
add path 'da[3-9]*' mode 0660 group operator.
```

This command will avoid the first three SCSI disks (da 0 to 2) from the operator group. You can replace 3 with other numbers of internal SCSI disks. Now enable the rule set in `/etc/rc.conf`.

- `devfs_system_ruleset="localrules"`

you can now instruct the user system to allow general users to mount their file system by reading the corresponding line to the command `/etc/sysctl.conf`:

- `vfs.usermount = 1`

This command takes effect right after the next reboot; you can use `sysctl` to set these variables.

- `# sysctl vfs.usermount=1`
- `vfs.usermount: 0 -> 1`

The last step is to develop a directory in which the user file system has to be mounted. This directory requires to be run by the same user that is to mount the actual file system. You can do this by developing a subdirectory on the same user as `/mnt/username`. In the following instance, replace `username` with the login name of the user and user group with the primary group of the user:

- `# mkdir /mnt/username`
- `# chown username:usergroup /mnt/username`

Suppose a USB thumb drive is plugged in, and the device `/dev/das0s1` appears. If the user device is formatted with a FAT file system, the user can mount it using:

- `% mount -t msdosfs -o -m=644,-M=755 /dev/da0s1 /mnt/username`

Before the user device gets unplugged, it has to be unmounted first

- `% umount /mnt/username`

The device is removed, the system message buffer will highlight the messages similar to

- `umass0: at uhub3, port 2, addr 3 (disconnected)`
- `da0 at umass-sim0 bus 0 scbus4 target 0 lun 0`
- `da0: <STECH Simple Drive 1.04> s/n WD-WXE508CAN263 detached`
- `(da0:umass-sim0:0:0:0): Periph destroyed`