

There are two ways to do this:

1. Load a kernel module for your sound card with `kldload`
2. Use the command line `# kldload snd_mujik`

Or you can add the appropriate line to the file `/boot/loader.conf` like `snd_mujik_load="YES"`

The other available sound drivers are listed in `/boot/defaults/loader.conf`. If you are not sure which driver to use, you can load the `snd_driver` module.



Sound Card

Copyright Attribution: Uploaded by WikimediaImages on Pixabay

Custom kernel configuration

Add the audio framework driver to the kernel by adding the following line:

- `device sound`

Next, add support for the sound card using the following command:

- `device snd_mujik`

Read the manual page of the driver for the syntax to use.

Non-PnP ISA sound cards will use the `snd_sbc(4)` driver simultaneously with `snd_sb16`. Add the following lines to the kernel configuration file:

- `device snd_sbc`
- `device snd_sb16`
- Similarly, add:
- `hint.sbc.0.at="isa"`
- `hint.sbc.0.port="0x220"`
- `hint.sbc.0.irq="5"`
- `hint.sbc.0.drq="1"`
- `hint.sbc.0.flags="0x15"`

to the `/boot/device.hints`, if the card uses the 0x220 I/O port and IRQ 5.